Cart counter's updating after adding the item in the cart

SeverityPriorityBehaviorTypeO NormalO MediumPositiveSmoke

LayerIs FlakyMilestoneAutomationNot setNo-Manual

Status Is Muted

Actual No

Pre-conditions

The user has been registered in the system earlier.

Parameters

Action

Input data

OS: Windows 11 Pro Version 23H2

Browser: Google Chrome Version 127.0.6533.120

Add any item to the cart.

Samsung Air 12 (1 piece)

Steps to reproduce

Step	1
Action	Open the login page.
Input data	https://qa.demoshopping.ru/login
Expected resul	tThe page is opened.
Step	2
Action	Sign in the system using existing username and password.
Input data	the username: Denisova_90 the password: HKdasej9a1A
Expected resu	tThe user is signed in successfully, no error message.
Step	3
Action	Go to the seventh page of the product catalog using pagination.
Input data	
Expected resultThe page is opened, no error message.	
Step	4

Expected resultThe item is added to the cart successfully, the cart counter changed to 1 automatically, no error message.

Step	5
Action	Go to the first page of the product catalog using pagination.
Input data	
Expected resu	IltThe page is opened, no error message.
Step	6
Action	Add 3 pieces of any item to the cart.
Input data	Apple Gaming 10 (3 pieces)

Expected resultThe item is added to the cart successfully, the cart counter changed to 4 automatically, no error message.

Cart counter's updating after deleting the item from the cart

Severity **Priority Behavior** Type O Normal O Medium Positive Smoke Layer Is Flaky Milestone **Automation** Not set No Manual Status Is Muted Actual No

Pre-conditions

The user has been registered in the system earlier.

Parameters

OS: Windows 11 Pro Version 23H2

Browser: Google Chrome Version 127.0.6533.120

Step	1
Action	Open the login page.
Input data	https://qa.demoshopping.ru/login
Expected result	The page is opened.
Step	2
Action	Sign in the system using existing username and password.
Input data	the username: Denisova_90 the password: HKdasej9a1A
Expected result	The user is signed in successfully, no error message.
Step	3
Action	Go to the second page of the product catalog using pagination.
Input data	
Expected result	The page is opened, no error message.
Step	4
Action	Add 2 pieces of any item to the cart.
Input data	Apple Studio 6 (2 pieces)

Expected result	The items are added to the cart successfully, the cart counter changed to 2 automatically, no error messag e.
Step	5
Action	Go to the ninth page of the product catalog using pagination.
Input data	
Expected result	The page is opened, no error message.
Step	6
Action	Add 3 pieces of any item to the cart.
Input data	Xiaomi Galaxy 3 (3 pieces)
Expected result	The items are added to the cart successfully, the cart counter changed to 5 automatically, no error messag e.
Step	7
Action	Go to the cart.
Input data	
Expected result	The cart page is opened successfully, no error message.
Step	8
Action	Delete one type of product that was added on the step 4.
Input data	Apple Studio 6 (2 pieces)
Expected result	The items are deleted, the cart counter changed to 3 automatically, no error message.

Cart counter's hiding after log out

Severity **Priority Behavior** Type ☆ Critical Positive Smoke ↑ High Layer Is Flaky Milestone **Automation** Manual Not set No Status Is Muted Actual No

Pre-conditions

The user has been registered in the system earlier.

Parameters

OS: Windows 11 Pro Version 23H2

Browser: Google Chrome Version 127.0.6533.120

Step	1
Action	Open the login page.
Input data	https://qa.demoshopping.ru/login
Expected result	The page is opened.
Step	2
Action	Sign in the system using existing username and password.
Input data	the username: Denisova_90 the password: HKdasej9a1A
Expected result	The user is signed in successfully, no error message.
Step	3
Action	Go to the third page of the product catalog using pagination.
Input data	
Expected result	The page is opened, no error message.
Step	4
Action	Add any 2 items to the cart (different products).

Input data	Apple Ultra 20 (1 piece), Apple Watch 11 (1 piece)
Expected result	The items are added to the cart successfully, the cart counter changed to 2 automatically, no error messag e.
Step	5
Action	Go to the sixth page of the product catalog using pagination.
Input data	
Expected result	The page is opened, no error message.
Step	6
Action	Add any item to the cart.
Input data	Huawei Note 10 (1 piece)
Expected result	The item is added to the cart successfully, the cart counter changed to 3 automatically, no error message.
Step	7
Action	Log out the system
Input data	
Expected result	The cart counter is hidden.

Item's quantity changing using control buttons in the cart

Severity **Priority Behavior** Type Positive Major O Medium Smoke Is Flaky Milestone **Automation** Layer Manual Not set No Status Is Muted Actual No

Pre-conditions

The user has been registered in the system earlier.

Parameters

OS: Windows 11 Pro Version 23H2

Browser: Google Chrome Version 127.0.6533.120

Step	1
Action	Open the login page.
Input data	https://qa.demoshopping.ru/login
Expected result	The page is opened.
Step	2
Action	Sign in the system using existing username and password.
Input data	the username: Denisova_90 the password: HKdasej9a1A
Expected result	The user is signed in successfully, no error message.
Step	3
Action	Go to the third page of the product catalog using pagination.
Input data	
Expected result	The page is opened, no error message.
Step	4
Action	Add any item to the cart.

Input data	Huawei Active 10 (1 piece)
Expected result	The item is added to the cart successfully, the cart counter changed to 1 automatically, no error message.
Step	5
Action	Go to the cart page.
Input data	
Expected result	The page is opened successfully.
Step	6
Action	Change the quantity of the item to 15 using control buttons.
Input data	
Expected result	The quantity of the items is changed to 15 successfully, the cart counter changed to 15 automatically, no err or message.

Item's quantity changing to 2000000 using input field in the cart

Severity **Priority Behavior Type** Major ↑ High Negative Smoke Is Flaky Milestone **Automation** Layer Not set No Manual Status Is Muted Actual No

Pre-conditions

The user has been registered in the system earlier.

Parameters

OS: Windows 11 Pro Version 23H2

Browser: Google Chrome Version 127.0.6533.120

Steps to reproduce

Step	1
Action	Open the login page.
Input data	https://qa.demoshopping.ru/login
Expected resu	ItThe page is opened.
Step	2
Action	Sign in the system using existing username and password.
Input data	the username: Denisova_90 the password: HKdasej9a1A
Expected resul	ItThe user is signed in successfully, no error message.
Step	3
Action	Go to the fifth page of the product catalog using pagination.
Input data	
Expected resultThe page is opened, no error message.	
Step	4
Action	Add the Huawei iPhone 19 (1 piece) to the cart.
Input data	

Expected resultThe item is added to the cart successfully, the cart counter changed to 1 automatically, no error message.

Expected re	esultError message
Input data	
Action	Change the quantity of the item to 2 000 000.
Step	6
Expected re	esultThe page is opened successfully.
Input data	
Action	Go to the cart page.
Step	5

Item's quantity changing to 1999999 using input field in the cart

Severity **Priority Behavior Type** ↑ High O Normal Negative Smoke Is Flaky Milestone **Automation** Layer Not set No Manual Status Is Muted

Pre-conditions

Actual

The user has been registered in the system earlier.

No

Parameters

OS: Windows 11 Pro Version 23H2

Browser: Google Chrome Version 127.0.6533.120

Step	1
Action	Open the login page.
Input data	https://qa.demoshopping.ru/login
Expected res	sultThe page is opened.
Step	2
Action	Sign in the system using existing username and password.
Input data	the username: Denisova_90 the password: HKdasej9a1A
Expected res	ultThe user is signed in successfully, no error message.
Step	3
Action	Go to the fifth page of the product catalog using pagination.
Input data	
Expected res	ultThe page is opened, no error message.
Step	4
Action	Add the Huawei iPhone 19 (1 piece) to the cart.
Input data	
Expected res	sult The item is added to the cart successfully, the cart counter changed to 1 automatically, no error message.

Expected r	esultError message
Input data	
Action	Change the quantity of the item to 1 999 999.
Step	6
Expected r	esultThe page is opened successfully.
Input data	
Action	Go to the cart page.
Step	5

Visual display of the items in the cart

Severity **Priority Behavior** Type Positive Smoke Major ↑ High Layer Is Flaky Milestone **Automation** Manual Not set No Status Is Muted Actual No

Pre-conditions

The user has been registered in the system earlier.

Parameters

OS: Windows 11 Pro Version 23H2

Browser: Google Chrome Version 127.0.6533.120

Step	1
Action	Open the login page.
Input data	https://qa.demoshopping.ru/login
Expected result	The page is opened.
Step	2
Action	Sign in the system using existing username and password.
Input data	the username: Denisova_90 the password: HKdasej9a1A
Expected result	The user is signed in successfully, no error message.
Step	3
Action	Go to the second page of the product catalog using pagination.
Input data	
Expected result	The page is opened, no error message.
Step	4
Action	Add the Apple iPhone 11 per \$822 and the Apple iPhone 11 per \$312 to the cart.

Input data	Apple iPhone 11 per \$822 (1 piece);
mpac aaca	Apple iPhone 11 per \$312 (1 piece)
Expected result	The items are added to the cart successfully, the cart counter changed to 2 automatically, no error messag e.
Step	5
Action	Go to the fifth page of the product catalog using pagination.
Input data	
Expected result	The page is opened, no error message.
Step	6
Action	Add the Huawei Mi 3 per \$849 and the Huawei Mi 3 per \$293 to the cart.
Input data	Huawei Mi 3 per \$849 (1 piece); Huawei Mi 3 per \$293 (1 piece)
Expected result	The items are added to the cart successfully, the cart counter changed to 4 automatically, no error messag e.
Step	7
Action	Go to the cart page.
Input data	
Expected result	The page is opened, no error message.
Step	8
Action	Check an image, name, selected quantity, and price per item for every products in the cart.
Input data	
Expected result	The name of every items must different.

Matching the visual display of the cart to the layout

Severity **Priority Behavior Type** O Normal ↑ High Positive Smoke Is Flaky Milestone **Automation** Layer Not set No Manual Status Is Muted Actual No

Pre-conditions

- 1. The user has been registered in the system earlier.
- 2. Install the app PerfectPixel by WellDoneCode.
- 3. Export the layout "Cart with product" from Figma to the downloads on your PC.

Parameters

OS: Windows 11 Pro Version 23H2

Browser: Google Chrome Version 127.0.6533.120

Step	1
Action	Open the login page.
Input data	https://qa.demoshopping.ru/login
Expected result	The page is opened.
Step	2
Action	Sign in the system using existing username and password.
Input data	the username: Denisova_90 the password: HKdasej9a1A
Expected result	The user is signed in successfully, no error message.
Step	3
Action	Go to the first page of the product catalog.
Input data	
Expected result	The page is opened, no error message.
Step	4
Action	Add the Apple Fit 10 to the cart.

Input data	Apple Fit 10 (3 pieces)
Expected result	The items are added to the cart successfully, the cart counter changed to 3 automatically, no error messag e.
Step	5
Action	Add the Apple Fit 12 to the cart.
Input data	Apple Fit 12 (1 piece)
Expected result	The items is added to the cart successfully, the cart counter changed to 4 automatically, no error message.
Step	6
Action	Go to the cart page.
Input data	
Expected result	The page is opened, no error message.
Step	7
Action	Open the PerfectPixel by WellDoneCode in the extensions.
Input data	
Expected result	The PerfectPixel is opened.
Step	8
Action	Add the first layer to the PerfectPixel from the downloads (see step 3 of the pre-conditions)
Input data	
Expected result	The first layer is added.
Step	9
Action	Match the layout of the cart and the cart's page of the online store.
Input data	
Expected result	The layout of the cart and the cart's page of the online store is matching.

Item's quantity changing to 0 using input field in the cart

Severity **Priority Behavior** Type Major ↑ High Negative Smoke Is Flaky Milestone **Automation** Layer Manual Not set No Status Is Muted Actual No

Pre-conditions

The user has been registered in the system earlier.

Parameters

OS: Windows 11 Pro Version 23H2

Browser: Google Chrome Version 127.0.6533.120

Step	1
Action	Open the login page.
Input data	https://qa.demoshopping.ru/login
Expected result	The page is opened.
Step	2
Action	Sign in the system using existing username and password.
Input data	the username: Denisova_90 the password: HKdasej9a1A
Expected result	The user is signed in successfully, no error message.
Step	3
Action	Go to the last page of the product catalog using pagination.
Input data	
Expected result	The page is opened, no error message.
Step	4
Action	Change the quantity of any product to 5 using control buttons.
Input data	Xiaomi Pro 4 (5 pieces)

Expected result	The quantity of the product is changed to 5 successfully.
	_
Step	5
Action	Add the items from the previous step to the cart.
Input data	
Expected result	The items are added to the cart successfully, the cart counter changed to 5 automatically, no error messag e.
Step	6
Action	Go to the cart page.
Input data	
Expected result	The page is opened successfully.
Step	7
Action	Change the quantity of the item to 0.
Input data	
Expected result	Error message

Redirecting to the payment page

Severity **Priority Behavior** Type ☆ Critical Positive Smoke ↑ High Layer Is Flaky Milestone **Automation** Manual Not set No Status Is Muted Actual No

Pre-conditions

The user has been registered in the system earlier.

Parameters

OS: Windows 11 Pro Version 23H2

Browser: Google Chrome Version 127.0.6533.120

Step	1
Action	Open the login page.
Input data	https://qa.demoshopping.ru/login
Expected result	The page is opened.
Step	2
Action	Sign in the system using existing username and password.
Input data	the username: Denisova_90 the password: HKdasej9a1A
Expected result	The user is signed in successfully, no error message.
Step	3
Action	Go to the seventh page of the product catalog using pagination.
Input data	
Expected result	The page is opened, no error message.
Step	4
Action	Add any item to the cart.
Input data	Samsung Book 2 (2 pieces)

Expected result	The items are added to the cart successfully, the cart counter changed to 2 automatically, no error messag e.
Step	5
Action	Go to the cart page.
Input data	
Expected result	The page is opened successfully.
Step	6
Action	Click the button "Оформить заказ".
Input data	
Expected result	The user is redirected to the payment page.

Payment by valid Visa card with positive balance

Severity **Priority Behavior** Type ☆ Critical Positive ↑ High Smoke Layer Is Flaky Milestone **Automation** Manual Not set No Status Is Muted Actual No

Pre-conditions

The user has been registered in the system earlier.

Parameters

OS: Windows 11 Pro Version 23H2

Browser: Google Chrome Version 127.0.6533.120

Step	1	
Action	Open the login page.	
Input data	https://qa.demoshopping.ru/login	
Expected result The page is opened.		
Step	2	
Action	Sign in the system using existing username and password.	
Input data	the username: Denisova_90 the password: HKdasej9a1A	
Expected res	ult The user is signed in successfully, no error message.	
Step	3	
Action	Go to the forth page of the product catalog using pagination.	
Input data		
Expected result The forth page is opened, no error message.		
Step	4	
Action	Add the last item in the second row on this page to the cart.	
Input data	Huawei Galaxy 5 (1 piece)	
Expected res	ult The item is added to the cart successfully, the cart counter changed to 1, no error message.	

5 Step Action Go to the cart. Input data Expected result The cart page is opened successfully, no error message. 6 Step Action Click the button "Оформить заказ" Input data Expected result The button is active, the user is redirected to the payment page. 7 Step Action Select Visa using radio button. Input data Expected result Visa is selected successfully, no error message. Step 8 Action Fill in card's details into the corresponding fields. card code: 8820354696467284; CVV: 123; exp. date: 12/26; Input data card holder: Eva Kim; email: example@mail.ru; balance: 2000 Expected result The card's details are filled in successfully, no error message. 9 Step Action Click the button "Оформить заказ" Input data

Expected result The button is active, the payment was successful, the user is redirected to the history of the orders page.

Payment by valid Mastercard with negative balance

Severity **Behavior Priority** Type ♠ Critical Negative Smoke ↑ High Layer Is Flaky Milestone **Automation** Manual Not set No Status Is Muted Actual No

Pre-conditions

The user has been registered in the system earlier.

Parameters

OS: Windows 11 Pro Version 23H2

Browser: Google Chrome Version 127.0.6533.120

Step	1
Action	Open the login page.
Input data	https://qa.demoshopping.ru/login
Expected result	The page is opened.
Step	2
Action	Sign in the system using existing username and password.
Input data	the username: Denisova_90 the password: HKdasej9a1A
Expected result	The user is signed in successfully, no error message.
Step	3
Step	Go to the tenth page of the product catalog using pagination.
·	
Action Input data	
Action Input data	Go to the tenth page of the product catalog using pagination.
Action Input data Expected result	Go to the tenth page of the product catalog using pagination. The tenth page is opened, no error message.
Action Input data Expected result Step	Go to the tenth page of the product catalog using pagination. The tenth page is opened, no error message.

Step	5
Action	Go to the cart.
Input data	
Expected result	The cart page is opened successfully, no error message.
Step	6
Action	Click the button "Оформить заказ"
Input data	
Expected result	The button is active, the user is redirected to the payment page.
Step	7
Action	Select Mastercard using radio button.
Input data	
Expected result	Mastercard is selected successfully, no error message.
Step	8
Action	Fill in card's details into the corresponding fields.
Input data	card code: 3320643190265792; CVV: 112; exp. date: 12/26; card holder: Filipp Tatarenko; email: example6@mail.ru; balance: 0;
Expected result	The card's details are filled in successfully, no error message.
Step	9
Action	Click the button "Оформить заказ"
Input data	
Expected result	The button is active, error message, the user isn't redirected to the history of the orders page.

Payment by invalid Visa card with positive balance

Severity **Priority Behavior Type** ☆ Critical ↑ High Negative Smoke Is Flaky Milestone **Automation** Layer Not set Manual No Status Is Muted Actual No

Pre-conditions

The user has been registered in the system earlier.

Parameters

OS: Windows 11 Pro Version 23H2

Browser: Google Chrome Version 127.0.6533.120

Details invalid visa card: card code: 4340511554108849; CVV: 789; card expiry date: 1/20; cardholder: Elena Smirnova; email: example2@mail.ru; balance: 2000, card code: 0779330784258313; CVV: 234; card expiry

date: 6/26; cardholder: Roman Bogdanov; email: example3@mail.ru; balance: 2000, card code: 9181347306820824; CVV: 0; card expiry date: 12/26; cardholder: Polina Ponomareva; email:

example4@mail.ru; balance: 2000

Step	1
Action	Open the login page.
Input data	https://qa.demoshopping.ru/login
Expected result	The page is opened.
Step	2
Action	Sign in the system using existing username and password.
Input data	the username: Denisova_90 the password: HKdasej9a1A
Expected result	The user is signed in successfully, no error message.
Step	3
Action	Go to the forth page of the product catalog using pagination.
Input data	
Expected result	The forth page is opened, no error message.
Step	4
Action	Add the last item in the second row on this page to the cart.

Input data	Huawei Galaxy 5 (1 piece)
Expected result	The item is added to the cart successfully, the cart counter changed to 1, no error message.
Step	5
Action	Go to the cart.
Input data	
Expected result	The cart page is opened successfully, no error message.
Step	6
Action	Click the button "Оформить заказ"
Input data	
Expected result	The button is active, the user is redirected to the payment page.
Step	7
Action	Select Visa using radio button.
Input data	
Expected result	Visa is selected successfully, no error message.
Step	8
Action	Fill in card's details into the corresponding fields from Parameters "Details invalid visa card".
Input data	
Expected result	The card's details are filled in successfully, no error message.
Step	9
Action	Click the button "Оформить заказ"
Input data	
Expected result	The button is active, error message

Payment by valid Mastercard card with positive balance

Severity **Priority Behavior** Type ☆ Critical Positive ↑ High Smoke Layer Is Flaky Milestone **Automation** Manual Not set No Status Is Muted Actual No

Pre-conditions

The user has been registered in the system earlier.

Parameters

OS: Windows 11 Pro Version 23H2

Browser: Google Chrome Version 127.0.6533.120

Step	1
Action	Open the login page.
Input data	https://qa.demoshopping.ru/login
Expected resu	t The page is opened.
Step	2
Action	Sign in the system using existing username and password.
Input data	the username: Denisova_90 the password: HKdasej9a1A
Expected resu	t The user is signed in successfully, no error message.
Step	3
Action	Go to the seventh page of the product catalog using pagination.
Input data	
Expected resu	t The seventh page is opened, no error message.
Step	4
Action	Add the second item in the first row on this page to the cart.
Input data	Samsung Air 19 (1 piece)
Expected resu	t The item is added to the cart successfully, the cart counter changed to 1, no error message.

5 Step Action Go to the cart. Input data Expected result The cart page is opened successfully, no error message. 6 Step Click the button "Оформить заказ" Action Input data Expected result The button is active, the user is redirected to the payment page. 7 Step Action Select Mastercard using radio button. Input data Expected result Mastercard is selected successfully, no error message. Step 8 Action Fill in card's details into the corresponding fields. card code: 5248106661644884; CVV: 456; exp. date: 12/26; Input data card holder: Maria Mystopylo; email: example5@mail.ru; balance: 2000 Expected result The card's details are filled in successfully, no error message. 9 Step Action Click the button "Оформить заказ" Input data Expected result The button is active, the payment was successful, the user is redirected to the history of the orders page.

Payment by valid Visa card with negative balance

Severity **Priority Behavior** Type ☆ Critical Negative Smoke ↑ High Layer Is Flaky Milestone **Automation** Not set Manual No Status Is Muted Actual No

Pre-conditions

The user has been registered in the system earlier.

Parameters

OS: Windows 11 Pro Version 23H2

Browser: Google Chrome Version 127.0.6533.120

Step	
Action	Open the login page.
Input data	https://qa.demoshopping.ru/login
Expected result	The page is opened.
Step	2
Action	Sign in the system using existing username and password.
Input data	the username: Denisova_90 the password: HKdasej9a1A
Expected result	The user is signed in successfully, no error message.
Step	3
Step	Go to the forth page of the product catalog using pagination.
·	
Action Input data	
Action Input data	Go to the forth page of the product catalog using pagination.
Action Input data Expected result	Go to the forth page of the product catalog using pagination. The forth page is opened, no error message.
Action Input data Expected result Step	Go to the forth page of the product catalog using pagination. The forth page is opened, no error message.

Step	5
Action	Go to the cart.
Input data	
Expected result	The cart page is opened successfully, no error message.
Step	6
Action	Click the button "Оформить заказ"
Input data	
Expected result	The button is active, the user is redirected to the payment page.
Step	7
Action	Select Visa using radio button.
Input data	
Expected result	Visa is selected successfully, no error message.
Step	8
Action	Fill in card's details into the corresponding fields.
Input data	card code: 7178218557247775; CVV: 890; exp. date: 12/26; card holder: Sergei Maiboroda; email: example1@mail.ru; balance: 0;
Expected result	The card's details are filled in successfully, no error message.
Step	9
Action	Click the button "Оформить заказ"
Input data	
Expected result	The button is active, error message, the user isn't redirected to the history of the orders page.

Payment by invalid Mastercard with positive balance

Severity **Priority Behavior Type** ☆ Critical ↑ High Negative Smoke Is Flaky Milestone **Automation** Layer Not set No Manual Status Is Muted Actual No

Pre-conditions

The user has been registered in the system earlier.

Parameters

OS: Windows 11 Pro Version 23H2

Browser: Google Chrome Version 127.0.6533.120

Details invalid Mastercard: card code: 0307328035514696; CVV: 101; card expiry date: 1/20; cardholder: Aleksandr Gorunov; email: example7@mail.ru; balance: 2000, card code: 1151842195999505; CVV: 567; card expiry date: 6/26; cardholder: Marina Filatova; email: example8@mail.ru; balance: 2000, card code:

6107972359241284; CVV: 0; card expiry date: 12/26; cardholder: Nikita Ivashkevich; email:

example9@mail.ru; balance: 2000

Step	1
Action	Open the login page.
Input data	https://qa.demoshopping.ru/login
Expected result	The page is opened.
Step	2
Action	Sign in the system using existing username and password.
Input data	the username: Denisova_90 the password: HKdasej9a1A
Expected result	The user is signed in successfully, no error message.
Step	3
Action	Go to the sixth page of the product catalog using pagination.
Input data	
Expected result	The sixth page is opened, no error message.
Step	4
Action	Add the first item in the first row on this page to the cart.

Input data	Huawei Mi 5 (1 piece)
	The item is added to the cart successfully, the cart counter changed to 1, no error message.
Step	5
Action	Go to the cart.
Input data	
Expected result	The cart page is opened successfully, no error message.
	_
Step	6
Action	Click the button "Оформить заказ"
Input data	
Expected result	The button is active, the user is redirected to the payment page.
Step	7
Action	Select Mastercard using radio button.
Input data	
Expected result	Mastercard is selected successfully, no error message.
Step	8
Action	Fill in card's details into the corresponding fields from Parameters "Details invalid Mastercard".
Input data	
Expected result	The card's details are filled in successfully, no error message.
Ston	0
Step	9
Action	Click the button "Оформить заказ"
Input data	

Expected result The button is active, error message

Payment by valid PayPal account with positive balance

Severity **Priority Behavior** Type ☆ Critical Positive ↑ High Smoke Layer Is Flaky Milestone **Automation** Manual Not set No Status Is Muted Actual No

Pre-conditions

The user has been registered in the system earlier.

Parameters

OS: Windows 11 Pro Version 23H2

Browser: Google Chrome Version 127.0.6533.120

Step	1
Action	Open the login page.
Input data	https://qa.demoshopping.ru/login
Expected resul	t The page is opened.
Step	2
Action	Sign in the system using existing username and password.
Input data	the username: Denisova_90 the password: HKdasej9a1A
Expected resul	t The user is signed in successfully, no error message.
Step	3
Action	Go to the second page of the product catalog using pagination.
Input data	
Expected resul	t The second page is opened, no error message.
Step	4
Action	Add the second item in the first row on this page to the cart.
Input data	Apple iPhone 11 (1 piece)
Expected result The item is added to the cart successfully, the cart counter changed to 1, no error message.	

5 Step Action Go to the cart. Input data Expected result The cart page is opened successfully, no error message. 6 Step Action Click the button "Оформить заказ" Input data Expected result The button is active, the user is redirected to the payment page. 7 Step Action Select PayPal using radio button. Input data Expected result PayPal is selected successfully, no error message. Step 8 Action Fill in account's details into the corresponding fields. paypal_email: valid@email.com; status: valid; Input data balance: 2000 email: example10@mail.ru Expected result The account's details are filled in successfully, no error message. 9 Step Action Click the button "Оформить заказ" Input data

Expected result The button is active, the payment was successful, the user is redirected to the history of the orders page.

Payment by invalid PayPal account with positive balance

Severity	Priority	Behavior	Туре
☆ Critical	↑ High	Negative	Smoke
Layer	ls Flaky	Milestone	Automation
Not set	No	-	Manual
Status	Is Muted		
Actual	No		

Pre-conditions

The user has been registered in the system earlier.

Parameters

OS: Windows 11 Pro Version 23H2

Browser: Google Chrome Version 127.0.6533.120

Details invalid Paypal's account: email for PayPal: invalid@email.com; email for check: example11@mail.ru; status: invalid; balance: 2000, email for PayPal: blocked@email.com; email for check: example12@mail.ru;

status: blocked; balance: 2000

Step	1
Action	Open the login page.
Input data	https://qa.demoshopping.ru/login
Expected result	The page is opened.
Step	2
Action	Sign in the system using existing username and password.
Input data	the username: Denisova_90 the password: HKdasej9a1A
Expected result	The user is signed in successfully, no error message.
Step	3
Action	Go to the sixth page of the product catalog using pagination.
Input data	
Expected result	The sixth page is opened, no error message.
Step	4

Action	Add the first item in the first row on this page to the cart.
Input data	Huawei Mi 5 (1 piece)
Expected result	The item is added to the cart successfully, the cart counter changed to 1, no error message.
Step	5
Action	Go to the cart.
Input data	
Expected result	The cart page is opened successfully, no error message.
Step	6
Action	Click the button "Оформить заказ"
Input data	
Expected result	The button is active, the user is redirected to the payment page.
Step	7
Action	Select PayPal using radio button.
Input data	
Expected result	PayPal is selected successfully, no error message.
Step	8
Action	Fill in PayPal account's details into the corresponding fields from Parameters "Details invalid Paypal's account".
Input data	
Expected result	The details are filled in successfully, no error message.
Step	9
Action	Click the button "Оформить заказ"
Input data	
Expected result	The button is active, error message

The amount of a shipping fee in the total product cost

Severity **Priority Behavior** Type ☆ Critical Positive ↑ High Smoke Layer Is Flaky Milestone **Automation** Manual Not set No Status Is Muted Actual No

Pre-conditions

The user has been registered in the system earlier.

Parameters

OS: Windows 11 Pro Version 23H2

Browser: Google Chrome Version 127.0.6533.120

Step	1
Action	Open the login page.
Input data	https://qa.demoshopping.ru/login
Expected result	The page is opened.
Step	2
Action	Sign in the system using existing username and password.
Input data	the username: Denisova_90 the password: HKdasej9a1A
Expected result	The user is signed in successfully, no error message.
Step	3
Action	Go to the fifth page of the product catalog using pagination.
Input data	
Expected result	The fifth page is opened, no error message.
Step	4
Action	Add any item with a shipping fee to the cart.
Input data	Huawei Mi 1 (1 piece)
Expected result	The item is added to the cart successfully, the cart counter changed to 1, no error message.

5 Step Action Go to the cart. Input data Expected result The cart page is opened successfully, no error message. 6 Step Action Click the button "Оформить заказ" Input data Expected result The button is active, the user is redirected to the payment page. Step 7 Action Compare the total product cost including a shipping fee and the product cost only. Input data

Expected result The different between the total product cost including a shipping fee and the product cost only is \$5.

Total product cost in the history of orders

SeverityPriorityBehaviorType♠ Critical↑ HighPositiveSmokeLaverIs FlakyMilestoneAutomation

Layer Is Flaky Milestone Automation

Not set No - Manual

Status Is Muted

Actual No

Pre-conditions

The user has been registered in the system earlier.

Parameters

OS: Windows 11 Pro Version 23H2

Browser: Google Chrome Version 127.0.6533.120

Steps to reproduce

Step 1

Action Open the login page.

Input data https://qa.demoshopping.ru/login

Expected result The page is opened.

Step 2

Action Sign in the system using existing username and password.

Input data the username: Denisova_90 the password: HKdasej9a1A

Expected result The user is signed in successfully, no error message.

Step 3

Action Add any three items to the cart.

Input data

Huawei iPhone 19 (1 piece) - 5th page
Samsung P30 2 (1 piece) - 8th page
Huawei Active 8 (1 piece) - 3th page

Expected result The items are added to the cart successfully, the cart counter changed to 3, no error message.

Step 4

Action Go to the cart .

Input data

Step	5
Action	Click the button "Оформить заказ"
Input data	
Expected re	sult The button is active, the user is redirected to the payment page.
Step	6
Action	Select Visa using radio button.
Input data	
Expected re	sult Visa is selected successfully, no error message.
Step	7
Action	Fill in card's details into the corresponding fields.
Input data	card code: 8820354696467284; CVV: 123; exp. date: 12/26; card holder: Eva Kim; email: example@mail.ru; balance: 2000
Expected re	sult The card's details are filled in successfully, no error message.
Step	8
Action	Click the button "Оформить заказ"
Input data	
Expected re	sult The button is active, the payment was successful, the user is redirected to the history of the orders page.
Step	9
Action	Check the total products cost in the history of the orders page.
Input data	
Expected re	sult The total products cost in the history of orders page is the same as the total products in the cart.

Expected result The cart page is opened successfully, no error message.

The payment date and delivery date

SeverityPriorityBehaviorType♠ Critical↑ HighPositiveSmokeLayerIs FlakyMilestoneAutomationNot setNo-Manual

Status Is Muted

Actual No

Pre-conditions

The user has been registered in the system earlier.

Parameters

OS: Windows 11 Pro Version 23H2

4

Go to the cart .

Step

Action

Input data

Browser: Google Chrome Version 127.0.6533.120

Step	1
Action	Open the login page.
Input data	https://qa.demoshopping.ru/login
Expected res	ult The page is opened.
Step	2
Action	Sign in the system using existing username and password.
Input data	the username: Denisova_90 the password: HKdasej9a1A
Expected res	ult The user is signed in successfully, no error message.
Step	3
Action	Add any three items to the cart.
Input data	Huawei iPhone 19 (1 piece) - 5th page Samsung P30 2 (1 piece) - 8th page Huawei Active 8 (1 piece) - 3th page
Expected res	ult The items are added to the cart successfully, the cart counter changed to 3, no error message.

Step	5
Action	Click the button "Оформить заказ"
Input data	
Expected res	ult The button is active, the user is redirected to the payment page.
Step	6
Action	Select Visa using radio button.
	Select visa using radio button.
Input data	
Expected res	ult Visa is selected successfully, no error message.
Step	7
Action	Fill in card's details into the corresponding fields.
Input data	card code: 8820354696467284; CVV: 123; exp. date: 12/26; card holder: Eva Kim; email: example@mail.ru; balance: 2000
Expected res	ult The card's details are filled in successfully, no error message.
Step	8
Action	Click the button "Оформить заказ"
Input data	
Expected res	ult The button is active, the payment was successful, the user is redirected to the history of the orders page.
Step	9
Action	Check the order date in the "Payment Date" column.
Input data	
Expected res	ult The date of order is matched with the payment date.

Expected result The cart page is opened successfully, no error message.

Displaying order history page

Severity **Priority Behavior Type** ☆ Critical Positive Smoke ↑ High Layer Is Flaky Milestone **Automation** Manual Not set No Status Is Muted Actual No

Pre-conditions

The user has been registered in the system earlier.

Parameters

OS: Windows 11 Pro Version 23H2

Browser: Google Chrome Version 127.0.6533.120

Open the login page.
https://qa.demoshopping.ru/login
The page is opened.
2
Sign in the system using existing username and password.
the username: Denisova_90 the password: HKdasej9a1A
The user is signed in successfully, no error message.
3
Go to the history of the orders page.
The page is opened.
4
Match the name of the column "Дата оплаты"
The column is named "Дата оплаты"

Step	5
Action	Match the name of the column "Дата поставки"
Input data	
Expected result	The column is named "Дата поставки"
Step	6
Action	Match the header of the table "История заказов"
Input data	
Expected result	The header is named "История заказов"