## **Systems Programming in C/C++**

Mohammed Bahja School of Computer Science University of Birmingham

#### **Outline of the module**

- Computer architecture: programmer's perspective
- C programming
  - Structure of a C program
  - Pointers and memory management
  - Applications of memory management
- Programming with threads
- Kernel programming ans OS topics

#### What this module is Not

- Not a 'Computer Architecture' module.
- This module is different from non-CS modules on C
- Not a re-run of Software Workshop
- Not a C++ software development module

#### **Assessment**

- 50% exam, 50% coursework
- Description of coursework and assessment criteria will be made available on Canvas.
- There will be 3 challenging assignments.
   (lab sessions will start from the second week).
- Make use of the labs (initially two hours per week) to work on the coursework problems.
- Will use virtual machine for exercises; see Canvas for details.

#### **Study materials**

- Recommended Course Books
  - The C Programming Language (2nd Edition) Kernighan and Ritchie
  - OS Concepts (10th Edition) Silberschatzet al.


## **Computers**













#### **Computers: two types**

From application point of view, computers can be classified into two major categories.






Can perform specific tasks.

E.g. only simple calculations.

Application Specific Computer


Can perform different tasks. E.g. calculations, watch movies, play games, browse internet etc.

**General Purpose Computer** 



Enigma machine used during World War II (Photo of the machine at The Alan Turing Institute, London)

Can perform only encryptions → hence application specific



'British bombe' an electromechanical computer designed by Alan Turing to break codes produced by the Enigma machine

#### Major bottleneck: Programming required major re-wiring.



Snap from movie "The Imitation Game". Benedict Cumberbatch as Alan Turing.

## **Stored Program Computers**

 The invention of stored program computers has been ascribed to John von Neumann.




 Stored-program computers have become known as 'von Neumann Architecture' systems.

A 'stored-program computer' is a computer that stores program instructions in memory.

→ Re-programming does not require any hardware modifications.

#### The von Neumann Architecture




#### Consists of three main components

- 1. Central Processing Unit (CPU)
- 2. Memory
- 3. Input/Output (I/O) interfaces.

The CPU can be considered the heart of the computing system. It includes two main components:

- 1. Control Unit (CU),
- 2. Arithmetic and Logic Unit (ALU)




ALU performs the mathematical or logical operations.

#### Example:

```
main()
{
    int a=5, b=6, c;
    c = a*b;
    c = c + b
}
```


The CPU can be considered the heart of the computing system. It includes two main components:

- 1. Control Unit (CU),
- 2. Arithmetic and Logic Unit (ALU)




The CPU can be considered the heart of the computing system. It includes two main components:

- 1. Control Unit (CU),
- 2. Arithmetic and Logic Unit (ALU)



The CPU can be considered the heart of the computing system. It includes two main components:

- 1. Control Unit (CU),
- 2. Arithmetic and Logic Unit (ALU)



Control Unit determines the order in which instructions should be executed and controls the retrieval of the proper operands.


Example:

```
main()
{
    int a=5, b=6, c;
    c = a*b;
    c = c + b
```

- 1. Retrieves the operands
- 2. Asks ALU to compute \*
- 3. Stores the result
- 4. Jumps to the next line


## **The Memory**

The computer's memory is used to store both program instructions and data.





## The Input/Output Interfaces


- The I/O interfaces are used to receive or send information from/to connected devices.
- Connected devices are called peripheral devices.





```
A program is stored in the memory.
    readIO a;
    readIO b;
   c = a + b;
    store c;
   d = a - b;
   print d;
                 ALU
                                   1/0
Memory
                                interfaces
                Control
                 Unit
                  CPU
```


















## **Organization of a CPU**

## Inside a CPU: Arithmetic and Logic Unit


 Arithmetic and Logic Unit (ALU) is the union of the circuits for performing arithmetic and logical operations.




 Control Unit is responsible for step-by-step execution of instructions during a program execution.

## **Inside a CPU: Registers**

- Registers are small storage elements that are located very close to the ALU.
- Registers are used as temporary storage during computation.
- ALU can read from and write to registers very fast.





von Neumann Architecture has three main components


- 1. Central Processing Unit (CPU)
- 2. Memory
- 3. Input/Output interfaces.

CPU need not have Registers. We can use Memory to store all data.

Consider this computation: c = a\*b + a + b + (a-b)\*a


Consider this computation: c = a\*b + a + b + (a-b)\*a

#### **Case 1: without registers**



Consider this computation: c = a\*b + a + b + (a-b)\*a

**Case 1: without registers** 




**Computation steps** 

1. read {a,b} from memory

Consider this computation: c = a\*b + a + b + (a-b)\*a

**Case 1: without registers** 




**Computation steps** 

- 1. read {a,b} from memory
- 2. compute c = a\*b

Consider this computation: c = a\*b + a + b + (a-b)\*a

**Case 1: without registers** 




**Computation steps** 

- 1. read {a,b} from memory
- 2. compute c = a\*b
- 3. store c in memory

Consider this computation: c = a\*b + a + b + (a-b)\*a

#### **Case 1: without registers**




#### **Computation steps**

- 1. read {a,b} from memory
- 2. compute c = a\*b
- 3. store c in memory
- 4. read {a,c} from memory
- 5. compute c = c + a
- 6. store c

Consider this computation: c = a\*b + a + b + (a-b)\*a

#### **Case 1: without registers**



Performance of a computer is measured in 'time requirement' for a task. Assume that


- Each memory read/write takes
   4 milliseconds
- Each arithmetic takes 1 millisecond.

#### Computation steps (all)

- 1. read {a,b} from memory
- 2. compute c = a\*b
- 3. store c in memory
- 4. read {a,c} from memory
- 5. compute c = c + a
- 6. store c
- 7. read {b,c} from memory
- 8. compute c = c + b
- 9. store c
- 10. read {a,b} from memory
- 11. compute c' = a-b
- 12. store c' in memory
- 13. read {c',a} from memory
- 14. compute c' = c'\*a
- 15. store c' in memory
- 16. read {c,c'} from memory
- 17. compute c = c+c'
- 18. store c in memory

Consider this computation: c = a\*b + a + b + (a-b)\*a

#### **Case 1: without registers**



In this particular computation, No. memory read/write = 12 No. arithmetic = 6


Hence, total time = 12\*4 + 6\*1 = 54 milliseconds

#### Computation steps (all)

- 1. read {a,b} from memory
- 2. compute c = a\*b
- 3. store c in memory
- 4. read {a,c} from memory
- 5. compute c = c + a
- 6. store c
- 7. read {b,c} from memory
- 8. compute c = c + b
- 9. store c
- 10. read {a,b} from memory
- 11. compute c' = a-b
- 12. store c' in memory
- 13. read {c',a} from memory
- 14. compute c' = c'\*a
- 15. store c' in memory
- 16. read {c,c'} from memory
- 17. compute c = c+c'
- 18. store c in memory

Consider this computation: c = a\*b + a + b + (a-b)\*a

#### **Case 2: with registers**




#### Two assumptions:

- 1. Initially, a and b are in Memory
- 2. ALU can read/write registers in0 time overhead

Consider this computation: c = a\*b + a + b + (a-b)\*a

#### **Case 2: with registers**



#### Two assumptions:


- 1. Initially, a and b are in Memory
- 2. ALU can read/write registers in 0 time overhead

#### Idea:

We read {a, b} from memory **only once** and then use the Registers to sore all intermediate data.

Consider this computation: c = a\*b + a + b + (a-b)\*a


#### **Case 2: with registers**



1. Read {a, b} from memory and load them in {Register1, Register2} 2. Read {Register1, Register2}, compute c=a\*b and store c in Register3 3. Read {Register3, Register1}, compute c=c+a and store c in Register3 4. Read {Register3, Register2}, compute c=c+b and store c in Register3 5. Read {Register1, Register2}, compute c'=a-b and store c' in Register4 6. Read {Register1, Register4}, compute c'=a\*c' and store c' in Register4 7. Read {Register3, Register4}, compute c=c+c' and store c in Register3 8. Finally, copy c from Register3 to Memory

Consider this computation: c = a\*b + a + b + (a-b)\*a

#### **Case 2: with registers**



Pure arithmetic entirely within CPU.


Register reads or writes have zero-time overhead.

Only two memory read/write

1. Read {a, b} from memory and load them in {Register1, Register2} Read {Register1, Register2}, compute c=a\*b and store c in Register3 3. Read {Register3, Register1}, compute c=c+a and store c in Register3 4. Read {Register3, Register2}, compute c=c+b and store c in Register3 5. Read {Register1, Register2}, compute c'=a-b and store c' in Register4 6. Read {Register1, Register4}, compute c'=a\*c' and store c' in Register4 -7. Read {Register3, Register4}, compute c=c+c' and store c in Register3 8. Finally, copy c from Register3 to Memory

Consider this computation: c = a\*b + a + b + (a-b)\*a

#### **Case 2: with registers**




Total time requirement = 2\*4 + 6\*1 = 14 milliseconds

1. Read {a, b} from memory and load them in {Register1, Register2} 2. Read {Register1, Register2}, compute c=a\*b and store c in Register3 3. Read {Register3, Register1}, compute c=c+a and store c in Register3 4. Read {Register3, Register2}, compute c=c+b and store c in Register3 5. Read {Register1, Register2}, compute c'=a-b and store c' in Register4 6. Read {Register1, Register4}, compute c'=a\*c' and store c' in Register4 7. Read {Register3, Register4}, compute c=c+c' and store c in Register3 8. Finally, copy c from Register3 to Memory


Consider this computation: c = a\*b + a + b + (a-b)\*a

#### **Case 1: without registers**



Total time requirement = 12\*4 + 6\*1 = 54 milliseconds

#### **Case 2: with registers**



Total time requirement = 2\*4 + 6\*1 = 14 milliseconds


#### **Conclusion: Registers improve processing speed**

All present-day computers have Registers inside CPUs


### **Updated: Inside a CPU**

So far, we have the following components inside a CPU

- Arithmetic and Logic Unit (ALU)
- Registers (new component for improving performance)
- Control Unit



### **Recap: The von Neumann Architecture**




#### Consists of three main components

- 1. Central Processing Unit (CPU) (we have covered the CPU)
- Memory (our next topic)
- 3. Input/Output interfaces.

## **Organization of Memory**


## **Memory**




Programmer sees memory as a storage element.

Programmer's View: Memory as an addressable

storage



- Memory consists of small 'cells'
- Each cell can store a small piece of data
- The cells have addresses. E.g. 0 to N-1





- During Read and Store operations, CPU generates memory addresses.
- Memory Management Unit (MMU) reads or writes from/to the requested memory-location.


```
main(){
    read a;
    read b;
    c = a + b;
    store c;
}
```

High-level code

Assume that programmer or compiler has allocated variables 'a', 'b' and 'c' in the memory locations with address #0, #1 and #2.








Assume that programmer or compiler has allocated variables 'a', 'b' and 'c' in the memory locations with address #0, #1 and #2.


High-level code

CPU

#### Steps:

- 1. CPU asks MMU to fetch data from #0.
- MMU reads location with address #0 and returns value of 'a'.






Assume that programmer or compiler has allocated variables 'a', 'b' and 'c' in the memory locations with address #0, #1 and #2.

High-level code

CPU

#### Steps:

- 1. CPU asks MMU to fetch data from #0.
- 2. MMU reads location with address #0 and returns value of 'a'.
- 3. Similar steps for 'read b'



```
main(){
    read a;
    read b;
    c = a + b;
    store c;
}
```


Assume that programmer or compiler has allocated variables 'a', 'b' and 'c' in the memory locations with address #0, #1 and #2.


High-level code

CPU

#### Steps:

4. CPU computes sum 'c'






```
main(){
    read a;
    read b;
    c = a + b;
    store c;
}
```

High-level code

In **C programming**, you will learn how to work with memory addresses using **Pointers**.



#### **Conclusions**

- We have studied von Neumann architecture.
- Programmer sees memory as a storage element.
  - Memory consists of small 'cells'
  - Each cell can store a small piece of data
  - The cells have addresses. E.g. 0 to N-1

