

Edition MySQL Community Known issues/limitations **▼** Hide filters

Review the Known issues/limitations to learn about potential compatibility issues with specific database versions.

Show versions that support the Multi-AZ DB cluster Info Create a A Multi-AZ DB cluster with one primary DB instance and two readable standby DB instances. Multi-AZ DB clusters provide up to 2x faster transaction commit latency and automatic failover in typically under 35 seconds.

Show versions that support the Amazon RDS Optimized Writes Info Amazon RDS Optimized Writes improves write throughput by up to 2x at no additional cost.

Engine Version

MySQL 8.0.28

Templates

Choose a sample template to meet your use case.

Production

Use defaults for high availability and fast, consistent performance.

O Dev/Test

This instance is intended for development use outside of a production environment.

Free tier

Use RDS Free Tier to develop new applications, test existing applications, or gain hands-on experience with Amazon RDS. Info

Availability and durability

Deployment options Info

The deployment options below are limited to those supported by the engine you selected above.

Multi-AZ DB Cluster

Creates a DB cluster with a primary DB instance and two readable standby DB instances, with each DB instance in a different Availability Zone (AZ). Provides high availability, data redundancy and increases capacity to serve read workloads.

- Multi-AZ DB instance (not supported for Multi-AZ DB cluster snapshot)
 Creates a primary DB instance and a standby DB instance in a different AZ. Provides high availability and data redundancy, but the standby DB instance doesn't support connections for read workloads.
- Single DB instance (not supported for Multi-AZ DB cluster snapshot)
 Creates a single DB instance with no standby DB instances.

Settings

DB instance identifier Info

Type a name for your DB instance. The name must be unique across all DB instances owned by your AWS account in the current AWS Region.

my-db-1

The DB instance identifier is case-insensitive, but is stored as all lowercase (as in "mydbinstance"). Constraints: 1 to 60 alphanumeric characters or hyphens. First character must be a letter. Can't contain two consecutive hyphens. Can't end with a hyphen.

▼ Credentials Settings

Master username Info


Type a login ID for the master user of your DB instance.

masterusername

1 to 16 alphanumeric characters. The first character must be a letter.

Manage master credentials in AWS Secrets Manager

Master username Info
Type a login ID for the master user of your DB instance. masterusername
1 to 16 alphanumeric characters. The first character must be a letter.
Manage master credentials in AWS Secrets Manager Manage master user credentials in Secrets Manager. RDS can generate a password for you and manage it throughout its lifecycle.
If you manage the master user credentials in Secrets Manager, some RDS features aren't supported. <u>Learn more</u>
Auto generate a password Amazon RDS can generate a password for you, or you can specify your own password.
Master password Info
••••••
Constraints: At least 8 printable ASCII characters. Can't contain any of the following: / (slash), '(single quote), "(double quote) and @ (at sign).
Confirm master password Info
••••••
Instance configuration The DB instance configuration options below are limited to those supported by the engine that you selected above.
DB instance class Info
▼ Hide filters
Include previous generation classes



The minimum value is 20 GiB and the maximum value is 6,144 GiB

- (i) After you modify the storage for a DB instance, the status of the DB instance will be in storage-optimization. Your instance will remain available as the storage-optimization operation completes.


 Learn more [7]
- **▼** Storage autoscaling

Storage autoscaling Info

Provides dynamic scaling support for your database's storage based on your application's needs.

Enable storage autoscaling

Enabling this feature will allow the storage to increase after the specified threshold is



Choose the DB subnet group. The DB subnet group defines which subnets and IP ranges the DB instance can use in the VPC that you selected. default Public access Info Yes RDS assigns a public IP address to the database. Amazon EC2 instances and other resources outside of the VPC can connect to your database. Resources inside the VPC can also connect to the database. Choose one or more VPC security groups that specify which resources can connect to the database. O No RDS doesn't assign a public IP address to the database. Only Amazon EC2 instances and other resources inside the VPC can connect to your database. Choose one or more VPC security groups that specify which resources can connect to the database. VPC security group (firewall) Info Choose one or more VPC security groups to allow access to your database. Make sure that the security group rules allow the appropriate incoming traffic. Create new Choose existing Choose existing VPC security groups Create new VPC security group New VPC security group name Enter new VPC security group name Availability Zone Info No preference **RDS Proxy** RDS Proxy is a fully managed, highly available database proxy that improves application scalability, resiliency, and security. ☐ Create an RDS Proxy Info RDS automatically creates an IAM role and a Secrets Manager secret for the proxy. RDS Proxy has additional costs. For more information, see Amazon RDS Proxy pricing <a>C.

DB subnet group Info

Cortificate authority antional Ind

Certificate authority - <i>optional</i> Info Using a server certificate provides an extra layer of security by validating that the connection is being made to an Amazon database. It does so by checking the server certificate that is automatically installed on all databases that you provision.
rds-ca-2019 (default) Expiry: Aug 22, 2024
If you don't select a certificate authority, RDS chooses one for you.
▼ Additional configuration
Database port Info TCP/IP port that the database will use for application connections.
3306
Database authentication

Database authentication options Info

Password authentication

Authenticates using database passwords.

O Password and IAM database authentication

Authenticates using the database password and user credentials through AWS IAM users and roles

O Password and Kerberos authentication

Choose a directory in which you want to allow authorized users to authenticate with this DB instance using Kerberos Authentication.

Monitoring

Monitoring
Enable Enhanced monitoring Enabling Enhanced monitoring metrics are useful when you want to see how different processes or threads use the CPU.
▼ Additional configuration Database options, backup turned on, backtrack turned off, maintenance, CloudWatch Logs, delete protection turned off.
Database options
Initial database name Info
dbname
If you do not specify a database name, Amazon RDS does not create a database.
DB parameter group Info
default.mysql8.0 ▼
Option group Info
default:mysql-8-0 ▼
Backup Inable automated backups Creates a point-in-time snapshot of your database
↑ Please note that automated backups are currently supported for InnoDB storage engine only. If you are using MyISAM, refer to details here .

Backup retention period Info	
The number of days (1-35) for which automatic backups are kept.	
1 ▼ day	
Backup window Info	
The daily time range (in UTC) during which RDS takes automated backups.	
○ Choose a window	
No preference	
✓ Copy tags to snapshots	
Backup replication Info	
☐ Enable replication in another AWS Region	
Enabling replication automatically creates backups of your DB instance in the selected Region,	
for disaster recovery, in addition to the current Region.	
Log exports	
Select the log types to publish to Amazon CloudWatch Logs	
☐ Audit log	
☐ Error log	
General log	
□ Slow query log	
IAM role	
The following service-linked role is used for publishing logs to CloudWatch Logs.	
RDS service-linked role	
Maintenance	
Auto minor version upgrade Info	
▼ Enable auto minor version upgrade	
Enabling auto minor version upgrade will automatically upgrade to new minor versions as	
they are released. The automatic upgrades occur during the maintenance window for the	

Maintenance window Info Select the period you want pending modifications or maintenance applied to the database by Amazon RDS. Choose a window No preference Deletion protection Enable deletion protection Protects the database from being deleted accidentally. While this option is enabled, you can't delete the database.

Estimated Monthly costs

 DB instance
 12.41 USD

 Storage
 2.30 USD

 Total
 14.71 USD

This billing estimate is based on on-demand usage as described in Amazon RDS Pricing . Estimate does not include costs for backup storage, IOs (if applicable), or data transfer.

Estimate your monthly costs for the DB Instance using the AWS Simple Monthly Calculator .

Estimated monthly costs

The Amazon RDS Free Tier is available to you for 12 months. Each calendar month, the free tier will allow you to use the Amazon RDS resources listed below for free:

- 750 hrs of Amazon RDS in a Single-AZ db.t2.micro, db.t3.micro or db.t4g.micro Instance.
- 20 GB of General Purpose Storage (SSD).
- 20 GB for automated backup storage and any user-initiated DB Snapshots.

Learn more about AWS Free Tier. <a>[Z

Estimated monthly costs

The Amazon RDS Free Tier is available to you for 12 months. Each calendar month, the free tier will allow you to use the Amazon RDS resources listed below for free:

- 750 hrs of Amazon RDS in a Single-AZ db.t2.micro, db.t3.micro or db.t4g.micro Instance.
- 20 GB of General Purpose Storage (SSD).
- 20 GB for automated backup storage and any user-initiated DB Snapshots.


Learn more about AWS Free Tier. <a>[2]


When your free usage expires or if your application use exceeds the free usage tiers, you simply pay standard, pay-as-you-go service rates as described in the Amazon RDS Pricing page.

(1) You are responsible for ensuring that you have all of the necessary rights for any third-party products or services that you use with AWS services.


Cancel

Create database







The error was rectified by editing inbound values from the security group





Delete and add new rule – type-> all traffic, source—anywhere ipv4 and save rules




Re run the mysql workbench














Therefore database instance (rds) got connected to mysql workbench.