

Step 1: Booting sequence

Configuring virtual interfaces

```
Please Enter Login Name: super
Please Enter Password:
User login successful.

R4_G8_S1>enable
No password has been assigned yet...
R4_G8_S1#config t
R4_G8_S1(config)#vlan 10
R4_G8_S1(config-vlan-10)#untagged eth 1/1//1 to 1/1/4
Invalid input -> 1/1//1 to 1/1/4
Type ? for a list
R4_G8_S1(config-vlan-10)#untagged eth 1/1/1 to 1/1/4
Added untagged port(s) ethe 1/1/1 to 1/1/4 to port-vlan 10.
R4_G8_S1(config-vlan-10)#router-interface ve 10
R4_G8_S1(config-vlan-10)#vlan 20
R4_G8_S1(config-vlan-20)#untagged eth 1/1/5 to 1/1/8
Added untagged port(s) ethe 1/1/5 to 1/1/8 to port-vlan 20.
R4_G8_S1(config-vlan-20)#router-interface ve 20
R4_G8_S1(config-vlan-20)#show run
Current configuration:
!
ver 08.0.95kT213
!
stack unit 1
  module 1 icx7150-cl2-poe-port-management-module
  module 2 icx7150-2-copper-port-2g-module
  module 3 icx7150-2-sfp-plus-port-20g-module
!
!
global-stp
!
!
!
vlan 1 name DEFAULT-VLAN by port
  spanning-tree
!
vlan 10 by port
  untagged ethe 1/1/1 to 1/1/4
  router-interface ve 10
!
vlan 20 by port
  untagged ethe 1/1/5 to 1/1/8
--More--, next page: Space, next line: Return key, quit: Control-c^C
R4_G8_S1(config-vlan-20)#exit
R4_G8_S1(config)#show run
```

```
!
!  
!
vlan 1 name DEFAULT-VLAN by port  
    spanning-tree  
!  
vlan 10 by port  
    untagged ethe 1/1/1 to 1/1/4  
    router-interface ve 10  
!  
vlan 20 by port  
    untagged ethe 1/1/5 to 1/1/8  
--More--, next page: Space, next line: Return key, quit: Control-C^C  
R4_G8_S1(config-vlan-20)#exit  
R4_G8_S1(config)#show run  
Current configuration:  
!  
ver 08.0.95kT213  
!  
stack unit 1  
    module 1 icx7150-cl2-poe-port-management-module  
    module 2 icx7150-2-copper-port-2g-module  
    module 3 icx7150-2-sfp-plus-port-20g-module  
!  
!  
global-stp  
!  
!  
!  
vlan 1 name DEFAULT-VLAN by port  
    spanning-tree  
!  
vlan 10 by port  
    untagged ethe 1/1/1 to 1/1/4  
    router-interface ve 10  
!  
vlan 20 by port  
    untagged ethe 1/1/5 to 1/1/8  
    router-interface ve 20  
!  
!  
!  
!  
!  
!  
!  
!  
!  
!
```


Configuring interfaces

```
end
R4_G8_S1(config)#interface ve 10
R4_G8_S1(config-vif-10)#ip address 10.0.0.1/24
R4_G8_S1(config-vif-10)#interface ve 20
R4_G8_S1(config-vif-20)#ip address 20.0.1/24
Invalid input -> 20.0.1/24
Type ? for a list
R4_G8_S1(config-vif-20)#ip address 20.0.0.1/24
R4_G8_S1(config-vif-20)#
```

Verifying VLAN Connections and Showing Interfaces

```
R4_G8_S1>enable
No password has been assigned yet...
R4_G8_S1#show interface brief
```

Port	Link	State	Dupl	Speed	Trunk	Tag	Pvid	Pri	MAC	Name
1/1/1	Up	Forward	Full	1G	None	No	10	0	7047.7704.489c	
1/1/2	Down	None	None	None	None	No	10	0	7047.7704.489c	
1/1/3	Down	None	None	None	None	No	10	0	7047.7704.489c	
1/1/4	Down	None	None	None	None	No	10	0	7047.7704.489c	
1/1/5	Down	None	None	None	None	No	20	0	7047.7704.489c	
1/1/6	Down	None	None	None	None	No	20	0	7047.7704.489c	
1/1/7	Down	None	None	None	None	No	20	0	7047.7704.489c	
1/1/8	Down	None	None	None	None	No	20	0	7047.7704.489c	
1/1/9	Down	None	None	None	None	No	1	0	7047.7704.48a4	
1/1/10	Down	None	None	None	None	No	1	0	7047.7704.48a5	
1/1/11	Down	None	None	None	None	No	1	0	7047.7704.48a6	
1/1/12	Down	None	None	None	None	No	1	0	7047.7704.48a7	
1/2/1	Down	None	None	None	None	No	1	0	7047.7704.48a9	
1/2/2	Down	None	None	None	None	No	1	0	7047.7704.48aa	
1/3/1	Down	None	None	None	None	No	1	0	7047.7704.48ab	
1/3/2	Down	None	None	None	None	No	1	0	7047.7704.48ac	
mgmt1	Up	None	Full	1G	None	No	None	0	7047.7704.489c	

Port	Link	State	Dupl	Speed	Trunk	Tag	Pvid	Pri	MAC	Name
ve10	Up	N/A	N/A	N/A	None	N/A	N/A	N/A	7047.7704.489c	
ve20	Down	N/A	N/A	N/A	None	N/A	N/A	N/A	7047.7704.489c	

```
R4_G8_S1#
```

R4_G8_S1#show interface brief

Port	Link	State	Dupl	Speed	Trunk	Tag	Pvid	Pri	MAC	Name
1/1/1	Down	None	None	None	None	No	10	0	7047.7704.489c	
1/1/2	Down	None	None	None	None	No	10	0	7047.7704.489c	
1/1/3	Down	None	None	None	None	No	10	0	7047.7704.489c	
1/1/4	Down	None	None	None	None	No	10	0	7047.7704.489c	
1/1/5	Down	None	None	None	None	No	20	0	7047.7704.489c	
1/1/6	Down	None	None	None	None	No	20	0	7047.7704.489c	
1/1/7	Down	None	None	None	None	No	20	0	7047.7704.489c	
1/1/8	Down	None	None	None	None	No	20	0	7047.7704.489c	
1/1/9	Down	None	None	None	None	No	1	0	7047.7704.48a4	
1/1/10	Down	None	None	None	None	No	1	0	7047.7704.48a5	
1/1/11	Down	None	None	None	None	No	1	0	7047.7704.48a6	
1/1/12	Down	None	None	None	None	No	1	0	7047.7704.48a7	
1/2/1	Down	None	None	None	None	No	1	0	7047.7704.48a9	
1/2/2	Down	None	None	None	None	No	1	0	7047.7704.48aa	
1/3/1	Down	None	None	None	None	No	1	0	7047.7704.48ab	
1/3/2	Down	None	None	None	None	No	1	0	7047.7704.48ac	
mgmt1	Up	None	Full	1G	None	No	None	0	7047.7704.489c	

Port	Link	State	Dupl	Speed	Trunk	Tag	Pvid	Pri	MAC	Name
ve10	Down	N/A	N/A	N/A	None	N/A	N/A	N/A	7047.7704.489c	
ve20	Down	N/A	N/A	N/A	None	N/A	N/A	N/A	7047.7704.489c	

R4_G8_S1#

R4_G8_S1(config-vif-20)#show int brief

Port	Link	State	Dupl	Speed	Trunk	Tag	Pvid	Pri	MAC	Name
1/1/1	Up	Forward	Full	1G	None	No	10	0	7047.7704.489c	
1/1/2	Down	None	None	None	None	No	10	0	7047.7704.489c	
1/1/3	Down	None	None	None	None	No	10	0	7047.7704.489c	
1/1/4	Down	None	None	None	None	No	10	0	7047.7704.489c	
1/1/5	Down	None	None	None	None	No	20	0	7047.7704.489c	
1/1/6	Down	None	None	None	None	No	20	0	7047.7704.489c	
1/1/7	Up	Forward	Full	1G	None	No	20	0	7047.7704.489c	
1/1/8	Down	None	None	None	None	No	20	0	7047.7704.489c	
1/1/9	Down	None	None	None	None	No	1	0	7047.7704.48a4	
1/1/10	Down	None	None	None	None	No	1	0	7047.7704.48a5	
1/1/11	Down	None	None	None	None	No	1	0	7047.7704.48a6	
1/1/12	Down	None	None	None	None	No	1	0	7047.7704.48a7	
1/2/1	Down	None	None	None	None	No	1	0	7047.7704.48a9	
1/2/2	Down	None	None	None	None	No	1	0	7047.7704.48aa	
1/3/1	Down	None	None	None	None	No	1	0	7047.7704.48ab	
1/3/2	Down	None	None	None	None	No	1	0	7047.7704.48ac	
mgmt1	Up	None	Full	1G	None	No	None	0	7047.7704.489c	

Port	Link	State	Dupl	Speed	Trunk	Tag	Pvid	Pri	MAC	Name
ve10	Up	N/A	N/A	N/A	None	N/A	N/A	N/A	7047.7704.489c	
ve20	Up	N/A	N/A	N/A	None	N/A	N/A	N/A	7047.7704.489c	

R4_G8_S1(config-vif-20)#

Show Routing Table

```
R4_G8_S1(config)#show ip route
Total number of IP routes: 3
Type Codes - B:BGP D:Connected O:OSPF R:RIP S:Static; Cost - Dist/Metric
BGP Codes - i:iBGP e:eBGP
OSPF Codes - i:Inter Area l:External Type 1 2:External Type 2
STATIC Codes - v:Inter-VRF
```

	Destination	Gateway	Port	Cost	Type	Uptime
1	10.0.0.0/24	DIRECT	ve 10	0/0	D	2m26s
2	20.0.0.0/24	DIRECT	ve 20	0/0	D	0m31s
3	192.168.100.0/24	DIRECT	e mgmt1	0/0	D	20m50s

```
R4_G8_S1(config)#show ip int
```

Interface	IP-Address	OK?	Method	Status	Protocol	VRF
Eth mgmt1	192.168.100.82	YES	NVRAM	up	up	default-vrf
Ve 10	10.0.0.1	YES	manual	up	up	default-vrf
Ve 20	20.0.0.1	YES	manual	up	up	default-vrf

```
R4_G8_S1(config)#
```