




Router1

Physical Config CLI Attributes

```

Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#
Router(config)#
Router(config)#ip route 50.0.0.0 255.0.0.0 192.162.10.1
Router(config)#
Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#
Router#
Router#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route

Gateway of last resort is not set

      20.0.0.0/24 is subnetted, 1 subnets
C      20.20.20.0 is directly connected, FastEthernet0/0
S      50.0.0.0/8 [1/0] via 192.162.10.1
C      192.162.10.0/24 is directly connected, Serial2/0

```

Router0

Physical Config CLI Attributes

```

Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#
Router(config)#ip route 60.0.0.0 255.0.0.0 192.162.10.2
Router(config)#
Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console

```

Router0

Physical Config CLI Attributes

```
Router#
Router#configure terminal
Enter configuration commands, one per line. End with CNTRL/Z.
Router(config)#interface fastEthernet 0/0
Router(config-if)#
Router(config-if)#ip nat inside
Router(config-if)#
Router(config-if)#exit
Router(config)#
Router(config)#interface serial 2/0
Router(config-if)#
Router(config-if)#ip nat outside
Router(config-if)#
Router(config-if)#exit
Router(config)#
Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#
Router#
Router#show ip nat statistics
Total translations: 2 (2 static, 0 dynamic, 0 extended)
Outside Interfaces: Serial2/0
Inside Interfaces: FastEthernet0/0
Hits: 0 Misses: 0
Expired translations: 0
Dynamic mappings:
```

Router0

Physical Config CLI Attributes

```
Router#enable
Router#
Router#show ip nat translations
Router#configure terminal
Enter configuration commands, one per line. End with CNTRL/Z.
Router(config)#
Router(config)#ip nat inside source static 10.10.10.2 50.50.50.2
Router(config)#
Router(config)#ip nat inside source static 10.10.10.3 50.50.50.3
Router(config)#
Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console


Router#
Router#
Router#show ip nat translations
Pro Inside global Inside local Outside local Outside global
--- 50.50.50.2 10.10.10.2 --- ---
--- 50.50.50.3 10.10.10.3 --- ---
```

Router1

Physical Config CLI Attributes

```
Router#
Router#ping 192.162.10.1

Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 192.162.10.1, timeout is 2 seconds:
!!!!
Success rate is 100 percent (5/5), round-trip min/avg/max = 7/10/16 ms
```



Show IP Routes (Router 0)

```

Router#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route
Gateway of last resort is not set
S 60.0.0.0/8 [1/0] via 192.162.10.2
C 192.162.10.0/24 is directly connected, Serial2/0

```

Show IP Routes (Router 1)

```

Router#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route
Gateway of last resort is not set
20.0.0.0/24 is subnetted, 1 subnets
C 20.20.20.0 is directly connected, FastEthernet0/0
S 50.0.0.0/8 [1/0] via 192.162.10.1
C 192.162.10.0/24 is directly connected, Serial2/0

```