
## KC27

### Создаём сеть:



# настраиваем роутер 0:

Router>en

Router#conf t

Enter configuration commands, one per line. End with CNTL/Z.

Router(config)#int fa0/0

Router(config-if)#ip ad 192.168.1.100 255.255.255.0

Router(config-if)#no sh

Router(config-if)#

%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

Router(config-if)#int fa4/0

Router(config-if)#ip ad 192.168.4.100 255.255.255.0

Router(config-if)#no sh

%LINK-5-CHANGED: Interface FastEthernet4/0, changed state to down

Router(config-if)#

Router(config-if)#ro eigrp 100

Router(config-router)#net 192.168.1.0

Router(config-router)#net 192.168.3.0

Router(config-router)#net 192.168.4.0

Router(config-router)#exit

Router(config)#

#### роутер 1:

Router>en

Router#conf t

Enter configuration commands, one per line. End with CNTL/Z.

Router(config)#int fa4/0

Router(config-if)#ip ad 192.168.3.200

% Incomplete command.

Router(config-if)#ip ad 192.168.3.200 255.255.255.0

Router(config-if)#no sh

Router(config-if)#

%LINK-5-CHANGED: Interface FastEthernet4/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet4/0, changed state to up

Router(config-if)#int fa5/0

Router(config-if)#ip ad 192.168.5.200 255.255.255.0

Router(config-if)#no sh

%LINK-5-CHANGED: Interface FastEthernet5/0, changed state to down

Router(config-if)#ro eigrp 100

Router(config-router)#net 192.168.3.0

Router(config-router)#net 192.168.5.0

Router(config-router)#exit

Router(config)#

#### роутер 3:

Router>en

Router#conf t

Enter configuration commands, one per line. End with CNTL/Z.

Router(config)#int fa4/0

Router(config-if)#ip ad 192.168.4.200 255.255.255.0

Router(config-if)#no sh

%LINK-5-CHANGED: Interface FastEthernet4/0, changed state to down

Router(config-if)#int fa5/0

Router(config-if)#ip ad 192.168.6.200 255.255.255.0

Router(config-if)#no sh

%LINK-5-CHANGED: Interface FastEthernet5/0, changed state to down

Router(config-if)#ro eigrp

٨

% Invalid input detected at '^' marker.

Router(config-if)#ro eigrp 100

Router(config-router)#net 192.168.4.0

Router(config-router)#

Router(config-router)#net 192.168.6.0

Router(config-router)#exit

## роутер 2:

Router(config)#int fa0/0

Router(config-if)#ip ad 192.168.2.100 255.255.255.0

Router(config-if)#no sh

Router(config-if)#

%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

Router(config-if)#int fa5/0

Router(config-if)#ip ad 192.168.6.100 255.255.255.0

Router(config-if)#no sh

Router(config-if)#

%LINK-5-CHANGED: Interface FastEthernet5/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet5/0, changed state to up

Router(config-if)#ro eigrp 100

Router(config-router)#net 192.168.2.0

Router(config-router)#net 192.168.5.0

Router(config-router)#net 192.168.6.0

## проверяем:

