




SSTP VPN setup guide for Windows 7

Access anything from anywhere in the world.


Step 1

To connect with SSTP you will need to install our CA certificate.

To get started type "certmgr.msc" in your Start -> Quick program box and hit Enter.



In the "Certificates" console right click "Trusted Root Certification Authorities" and select All Task -> Import.




Step 2

Click "Next".




Step 3

a) Click "Browse".




b) Select the certnew.cer file we sent you in the greeting mail and click Open.



c) Click "Next".

Step 4

a) Select the "Place all certificates in the following store" option and click "Browse."




b) Check "Show physical stores".

Select the "Trusted Root

Certification Authorities ->


-> Local computer" and click "OK".



c) Click "Next".

Step 5

Click on "Finish" and then on "OK". You have successfully imported the certificate !




Step 6


Save the "NoCRLCheck.reg" file from your greeting mail to your computer and double click on it.

Name	Date modified	Type	Size
certnew	7/10/2010 10:20 PM	Security Certificate	1 KB
NoCRLCheck	7/19/2010 7:56 PM	Registration Entries	1 KB

Select "Yes". This will add a new key in your registry to optimize SSTP VPN performance.




You have successfully imported the key. Click "OK".



Step 7

Go to the Windows 7 Start Button and click on "Control Panel".

In "Control Panel" click on "Network and Sharing Center".



Step 8

In the "Network and Sharing Center" click on "Setup a new connection or network".

Change your networking settings



[Set up a new connection or network](#)

Set up a wireless, broadband, dial-up, ad hoc, or VPN connection; or set up a router or access point.



[Connect to a network](#)

Connect or reconnect to a wireless, wired, dial-up, or VPN network connection.



[Choose homegroup and sharing options](#)

Access files and printers located on other network computers, or change sharing settings.




[Troubleshoot problems](#)

Diagnose and repair network problems, or get troubleshooting information.


Step 9

Select "Connect to a workspace" and click "Next"



Step 10

Click "Use my Internet connection".




Step 11

Enter the server address from your greeting mail in the Internet Address box.


Enter "High Speed VPN" for destination name. Click "Next".

Check the "Don't connect now" option.




Step 12

**Enter your High Speed VPN Account details we provided you with in the greeting mail.
Check the "Remember this password" box if you want to save the password.
Click on "Create".**




Step 13

a) Select "Properties" on the "High Speed VPN" newly created connection.




b) Go to the "Security" tab and select "SSTP" as "Type of VPN". Click "OK" to save.




Step 14

- Click "Connect" on the "High Speed VPN" connection in the "Dial-up and VPN" tab.**
- Check the "Save this user name and password" box and click "Connect".**



Congratulations !

You are now connected to High Speed VPN:





Thank you for your time and consideration.

**Please contact us if you have any problems setting up
your connection with High Speed VPN.**

**We will answer as soon as possible,
but no more than 12 hours.**

Kind regards,

HVPN Team

support@highspeedvpn.com

<http://www.highspeedvpn.com>