
Ubuntu Server 20.04.2Adding GUI Desktop to Ubuntu Server

Waikato Linux Users Group Ian Stewart 2021-05-24

Ubuntu Server 20.04.2

- Does NOT run 'live' from a USB stick.
- Install Guide: https://ubuntu.com/server/docs/install/step-by-step
- Upon completing installation can add 'tasksel'
 \$ sudo apt install tasksel
 \$ tasksel
- Perform on-line adding and removing of the various GUI Desktop flavours using tasksel.

Tasksel options...



	[]	Kubuntu live CD	
		Lubuntu live CD	
1	[]	Ubuntu Budgie live CD	Г
1		Ubuntu live CD	ŀ
1	[]	Ubuntu MATE Live CD	ŀ
1	[]	Ubuntu Studio live DVD	ŀ
1	[]	Xubuntu live CD	ľ
1	[]	Ubuntu Cloud Image (instance)	[>
1	[]	DNS server]]] *]
1	[]	Kubuntu desktop	L
		LAMP server	
1	[]	Lubuntu Desktop	
1	[]	Mail server	
1	[]	PostgreSQL database	
		Print server	
1	[]	Samba file server	
	[]	Ubuntu Budgie desktop	
		Ubuntu desktop	
- 1		Ubuntu desktop default languages	
1	[]	Ubuntu minimal desktop	
1		Ubuntu minimal desktop default languages	
1		Ubuntu MATE minimal	
1	[*]	Ubuntu MATE desktop	
1		Audio recording and editing suite	
	[]	Ubuntu Studio desktop	
	[]	Ubuntu Studio minimal DE installation	
1	[]	Large selection of font packages	
	[]	2D/3D creation and editing suite	

*]	Photograph touchup and editing suite Publishing applications Video creation and editing suite Xubuntu minimal installation Xubuntu desktop OpenSSH server Basic Ubuntu server
J	Basic Ubuntu server

Ubuntu Server 20.04.2

After installing a GUI desktop the system will boot to a GUI.

Turn Desktop GUI off and go back to being a server with:

```
$ sudo systemctl set-default multi-user
...and do a...
$ startx
...when you want a GUI Desktop.
```

...or have GUI desktop on boot with...

\$ sudo systemctl set-default graphical