# Object Placement

# Table of Contents

Table of Contents
IntroductionIII
Script Reference
Scripts1
ObjectPlacement.cs1
ObjectPlacementEditor.cs
Bounds
APlacementBounds.cs
ColliderPlacementBounds.cs
CustomPlacementBounds.cs22
IPlacementBounds.cs
RendererPlacementBounds.cs24
Input
AInputControl.cs25
ActionInputControl.cs27
InputControlResponder.cs32
KeyInputControl.cs33
Cursor
DefaultMousePositionProvider.cs35
ICursorPositionProvider.cs36
Interface
IPlacingObject.cs36
IValidatePlacement.cs37
ObjectPlacementEvents.cs
ObjectPlacementObserver.cs40
PlacementPrefabs.cs41
PlacementPrefabsEditor.cs44
PlacementResult.cs45
PlacingObjectObserver.cs45
PlacementArea47
ASpherePlacementAreas.cs47
IPlacementArea.cs49
ObjectPlacementArea.cs49
ObjectPlacementAreaManager.cs51
PlacementAreaInfo.cs53
SpherePlacementAreaManager.cs55
Utility56

olliderBoundsHelper.cs5	6
ridSnapper.cs5	7
roundPlacement.cs5	9
nstantiatePlacementObject.cs6	1
ntRange.cs6	2
ntRangeAttribute.cs6	4
athHelper.cs6	5
phereBounds.cs6	6

# Introduction

Here you can read and quickly find code documentation of the asset package. For guide you can check out the set up guide and how it works section here: https://travljen.gitbook.io/object-placement/getting-started/add-object-placement-to-sce ne

## Script Reference

### **Scripts**

### ObjectPlacement.cs

### **Namespaces**

### TRavljen.PlacementSystem

namespace TRavljen.PlacementSystem

### **Enumerations**

### **GroundAlignmentType**

```
enum GroundAlignmentType{
   None,
   ValidateOnly,
   AlignToGround,
   LowestPoint}
```

Defines the alignment type of placing objects.

None: Object will not be aligned to ground, nor will they be validated.

ValidateOnly: Object will not be aligned to ground. It will only be validated based on rotation threshold.

AlignToGround: Object will align to ground with its edges touching the mesh or terrain below it, rotating X and Z axis to achieve it.

LowestPoint: Object will find which of its edges is the lowest on ground and position itself on it, without rotation.

### **Classes**

### ObjectPlacement

public class ObjectPlacement
: MonoBehaviour

#### **Variables**

#### \_instance

```
private static ObjectPlacement _instance
```

#### playerCamera

```
[Tooltip("Specifies the main camera which renders world to the player.")]
[SerializeField]
private Camera playerCamera
```

#### placementObjectPrefab

```
[Tooltip("Specifies the prefab used for placement. This may also be set during runtime, when the placement is not active.")]
[SerializeField]
private GameObject placementObjectPrefab
```

#### groundLayer

```
[Tooltip("Specifies the ground layer mask for ground detection." +
"Use the layer on which the objects should be placed,
commonly 'Ground' is used for terrains or ground planes.")]
[SerializeField]
private LayerMask groundLayer
```

#### maxDetectionDistance

```
[Tooltip("Specifies the maximal range allowed for ground detection from camera/cursor position.")]
[SerializeField, Range(10, 5_000)]
private float maxDetectionDistance
```

#### obstacleLayer

```
[Tooltip("Specifies the obstacles layer mask used for detecting for any " +
"objects that might be in the way, like environment or already placed objects.")]
[SerializeField]
private LayerMask obstacleLayer
```

#### destructablesLayer

```
[Tooltip("Specifies the layer of destructables used for detecting objects in placement bounds that may be destroyed when object is placed.")]
[SerializeField]
private LayerMask destructablesLayer
```

#### destroyDestructableOnPlacement

```
[Tooltip("Specifies if objects detected as destructable obstacles are destroyed on placement." +

"If this is set to false, you need to manage destruction with OnObjectDestroy event.")]

[SerializeField]

private bool destroyDestructableOnPlacement
```

#### ignoreWhenOverUI

```
[Tooltip("Specifies if the placement should be ignored when cursor is hovering over UI components.\n\n" +
"Example: If this is disabled, clicking a button on UI when placement is active will still trigger placement." +
"When enabled, such placement action will be ignored.")]
[SerializeField]
private bool ignoreWhenOverUI
```

#### placementArea

```
[SerializeField]
[Tooltip(
"Specifies the area of valid placement. This can restrict placement of objects outside of certain area.")]
private PlacementAreaInfo placementArea
```

#### groundAlignmentType

```
[Tooltip("Specifies if the object should visually align to the ground instead of the placement center. See 'GroundAlignmentType' for more information.")]
[SerializeField]
private GroundAlignmentType groundAlignmentType
```

#### groundAlignment

```
[SerializeField]
private GroundAlignment groundAlignment
```

#### groundAngleThreshold

```
[Tooltip("Specifies the angle range in which the object placement is valid, " +
"once angles go out of this bounds, placement is no longer valid. " +
"This ensures that the ground below it is flat enough for placement of objects.")]
[IntRange(0, 90)]
[SerializeField]
private IntRange groundAngleThreshold
```

#### rotationSpeed

```
[Tooltip("Specifies rotation speed. If holdToRotate is enabled, then this value will be multiplied with delta time on each update.")]
[SerializeField]
private float rotationSpeed
```

#### preserveRotation

```
[Tooltip("Specifies if the rotation between placements is preserved." +

"If a placement is canceled or finished, should the next
placement keep the Y rotation or reset to 0.")]

[SerializeField]

private bool preserveRotation
```

#### usePositionSnapping

```
[Tooltip("Specifies if the position snapping feature is enabled.")]
[SerializeField]
private bool usePositionSnapping
```

#### gridSnapper

```
[SerializeField]
private GridSnapper gridSnapper
```

#### applyPlacementMaterials

```
[Tooltip("Specifies if valid/invalid materials are applied to the placing object.")]
[SerializeField]
private bool applyPlacementMaterials
```

#### validPlacementMaterials

```
[Tooltip("Specifies a list of materials applied to placing object when placement is valid.")]
[SerializeField]
private Material[] validPlacementMaterials
```

#### invalidPlacementMaterials

```
[Tooltip("Specifies a list of materials applied to placing object when placement is invalid.")]
[SerializeField]
private Material[] invalidPlacementMaterials
```

#### allowPlacementDuringAnimations

```
[Tooltip("Specifies if placing an object is allowed during active movement or rotation animations." +
"When this is disabled 'animatingAngleThreshold' and 'animatingDistanceThreshold' will be used.")]
[SerializeField]
private bool allowPlacementDuringAnimations
```

#### animatingAngleThreshold

```
[Tooltip("Specifies what the max angle difference can be between target rotation " + "and current rotation, when placement during animation is not allowed.")]
[SerializeField, Range(0, 360)]
private float animatingAngleThreshold
```

#### animatingDistanceThreshold

```
[Tooltip("Specifies the max distance allowed between target position and current placing object, " + "when placement during animation is not allowed")]
[SerializeField, Range(0, 100)]
private float animatingDistanceThreshold
```

#### animatePositionChange

```
[Tooltip("Specifies if the position changes are animated. This means that if enabled, " +
"placing object will follow cursor with position change speed.")]
[SerializeField]
private bool animatePositionChange
```

#### positionChangeSpeed

```
[Tooltip("Specifies the speed of position change if the change is animated.")]
[SerializeField]
private float positionChangeSpeed
```

#### animateRotationChange

```
[Tooltip("Specifies if the rotation changes are animated. This means that if enabled, " + "placing object will rotate with the rotation change speed.")]
[SerializeField]
private bool animateRotationChange
```

#### rotationChangeSpeed

```
[Tooltip("Specifies the speed of rotation change if the change is animated.")]
[SerializeField]
private float rotationChangeSpeed
```

#### debugLogsEnabled

```
[Tooltip("Specifies if the console logging is enabled.")]
public bool debugLogsEnabled
```

#### drawGizmosEnabled

```
[Tooltip("Specifies if the gizmos for placement are enabled.")]
public bool drawGizmosEnabled
```

#### gizmoPlacementAreaColor

```
[Tooltip("Specifies the gizmo color for placement area.")]
[SerializeField]
Color gizmoPlacementAreaColor
```

#### gizmoPlacementBoundsColor

```
[Tooltip("Specifies the gizmo color for placing object's bounds.")]
[SerializeField]
Color gizmoPlacementBoundsColor
```

#### gizmoPlacementGroundPositionsColor

```
[Tooltip("Specifies the gizmo color for positions on ground under the placing object." +
"These are indicators of where the ground position was found for each edge of the bounds of the placing object.")]
[SerializeField]
Color gizmoPlacementGroundPositionsColor
```

#### AdditionalValidator

```
public IValidatePlacement AdditionalValidator
```

Validator invoked after internal validation has been performed with a valid result, if result is invalid this will not be invoked. Only already valid placements can be rejected by this validator.

#### CursorPositionProvider

```
public ICursorPositionProvider CursorPositionProvider
```

Cursor position provider reference. By default the DefaultMousePositionProvider is used. You can override this with any custom implementation of the ICursorPositionProvider interface.

#### *isPlacementActive*

private bool isPlacementActive

#### *isPlacementValid*

private bool isPlacementValid

#### targetPosition

private Vector3 targetPosition

#### targetRotationY

private float targetRotationY

#### *currentRotationY*

private float currentRotationY

### placingObjectTemplate

private Transform placingObjectTemplate

#### placingObjectBounds

 $private \ \textit{IPlacementBounds placingObjectBounds}$ 

#### colliderHits

private readonly Collider[] colliderHits

#### PlacementPrefabs

public PlacementPrefabs PlacementPrefabs

Returns placement prefab component if present. This must be enabled on ObjectPlacement component in Editor under "Prefabs" tab, otherwise null will be returned.

### **Properties**

#### Instance

```
public static ObjectPlacement Instance
    { get;
    }
```

Instance of currently active object placement. If second instance attempts to be instantiated, it will be destroyed on Awake.

#### **PlacementArea**

```
public PlacementAreaInfo PlacementArea
      { get;
           set;      }
```

Specifies the area of valid placement. This can restrict placement of objects outside of certain area.

#### PlacementObjectPrefab

```
public GameObject PlacementObjectPrefab
{ get;
}
```

Current prefab used when placement activates.

#### PlayerCamera

```
public Camera PlayerCamera
   { get;
   set; }
```

Sets and gets the current players camera used to render world objects. This camera is used for raycasts from screenpoint.

### **Methods**

#### **CurrentRotation**

```
private Quaternion CurrentRotation()
```

#### **IsPlacementActive**

```
public bool IsPlacementActive()
```

Getter for checking if object placement is currently active.

#### **OnValidate**

```
private void OnValidate()
```

#### Awake

```
private void Awake()
```

#### Start

```
private void Start()
```

#### **Update**

```
private void Update()
```

#### Enable

```
public void Enable()
```

Activates the game object.

#### Disable

```
public void Disable()
```

Deactivates the game object.

#### SetPlacementPrefab

Sets the new placement prefab. If placement is already active it will be cancelled and activated again with the new prefab.

prefab: New placement prefab

#### **BeginPlacement**

```
public void BeginPlacement(
          GameObject prefab)
```

Begins the placement with the new prefab game object. Placement materials remain unchanged.

prefab: New placement prefab

#### BeginPlacement

```
public void BeginPlacement(
   GameObject prefab,
   Material[] validPlacement,
   Material[] invalidPlacement)
```

Begins placement with passed prefab and optional materials. If visuals on placing objects are desired, you can use placement material arguments, IPlacingObject or PlacingObjectObserver to apply visuals for placement states out of the box.

prefab: Prefab reference to be used for placement

validPlacement: Materials applied to new instance of the prefab when placement is valid.

Default value is null, which does nothing.

invalidPlacement: Materials applied to new instance of the prefab when placement is invalid.

Default value is null, which does nothing.

#### BeginPlacement

```
public void BeginPlacement()
```

Begins placement with current PlacementObjectPrefab on current's mouse position.

#### CancelPlacement

```
public void CancelPlacement()
```

Cancels currently active placement.

#### **TryEndPlacement**

```
public bool TryEndPlacement(
  out GameObject newInstance,
  bool removeDestructables = true)
```

Attempts to end placement by instantiating a new object on the valid placement. If placement failed no object will be instantiated and placement will continue and not be cancelled.

newInstance: Reference to the new instance created removeDestructables: Specifies if destructables will be removed when placement ends. By default this is true

Returns: Returns true if new instance was created, returns false if placement was invalid.

#### ShouldIgnorePlacement

```
private bool ShouldIgnorePlacement()
```

Checks if placement should be ignored duo to cursor being over the UI components, like buttons, texts or images.

Returns: Returns true when placement should be ignored.

#### **TryEndPlacement**

```
public bool TryEndPlacement(
   out PlacementResult placementResult,
   bool removeDestructables = true)
```

Attempts to end placement by returning a valid position and rotation for the object currently placing. When placement is inactive or invalid false is returned along with default result values.

placementResult: Result values, set only in case of valid placement removeDestructables: Specifies if destructables will be removed when placement ends. By default this is true

Returns: Returns true if placement was valid, returns false if it was inactive or invalid.

#### InternalTryEndPlacement

```
private bool InternalTryEndPlacement(
  out PlacementResult placementResult,
  bool removeDestructables)
```

Method for internal use, does not invoke any events on ObjectPlacementEvents, but only performs common logic for both interfaces to end placement. Attempts to end currently active placement and destroys placingObjectTemplate if placement is successful.

placementResult: Result of placement. Default values are returned if placement failed.

Returns: Returns true if placement was valid, returns false if it was inactive or invalid.

#### ResetRotation

```
public void ResetRotation()
```

Resets current rotation for placing object. This can also be used if preserveRotation is enabled.

#### RotateObjectYAxis

```
public void RotateObjectYAxis(
    float yAngle)
```

Rotates currently placing object on Y axis by increasing current target Y angle.

yAngle: Y angle to add to object's current Y.

#### RotatePlacement

```
public void RotatePlacement(
   float directionalMagnitude)
```

Rotates currently placing object on Y axis by multiplying directional magnitude parameter with rotationSpeed.

directionalMagnitude: Y direction with magnitude.

#### UpdatePlacingObject

```
private void UpdatePlacingObject(
     bool animate)
```

Calculates placement position and rotation for the placing object, while validating and if needed updating renderer materials.

animate: If update should be animated. Applies to position and rotation changes.

#### **ValidatePlacement**

```
private bool ValidatePlacement(
    IPlacementBounds placingObject)
```

Validates placement bounds with ground alignment and bounds collision check.

placingObject: Placing objects bounds

Returns: Returns true if placement positon & rotation is valid.

#### TryGroundAlignment

```
private bool TryGroundAlignment(
Bounds bounds,
Quaternion rotation)
```

Performs ground alignment based on groundAlignmentType. When the type is GroundAlignmentType.ValidateOnly object will not be adjusted in position or rotation, but will still be validated based on ground angle threshold.

bounds: World space bounds rotation: World rotation

Returns: Returns true if the placement is within expected groundAngleThreshold.

#### CheckForCollisions

```
private int CheckForCollisions(
Bounds bounds,
Quaternion rotation,
LayerMask layer)
```

Performs Physics overlapping collision check with specified bounds and rotation.

bounds: World space bounds rotation: World rotation layer: Layer for collision

Returns: Returns true if there are NO colliders in the way.

#### **UpdatePlacementMaterials**

```
private void UpdatePlacementMaterials(
    Transform placingObject,
    bool isValid)
```

Updates materials on all child Renderer components. In case no materials are set, this does nothing.

placingObject: Root transform of the object

isValid: If placement is valid

#### **GetPlacementPosition**

```
private Vector3 GetPlacementPosition()
```

Shoots raycast based on current cursor position, validates the hit point and returns a validated position (snap and clamp features). In case of failure the last valid position is returned.

Returns: Returns validated position for the placement of an object.

#### GetPlacingObjectComponent

Gets a component that implements IPlacingObject.

#### RemoveDestructables

```
private void RemoveDestructables(
    Bounds bounds,
    Quaternion rotation)
```

Removes objects with colliders within the specified bounds and rotation.

bounds: Bounds of placed object. rotation: Rotation of placed object.

#### **OnDrawGizmos**

```
private void OnDrawGizmos()
```

### ObjectPlacementEditor.cs

### **Namespaces**

### TRavljen.PlacementSystem.Editor

namespace TRavljen.PlacementSystem.Editor

#### Classes

### ObjectPlacementEditor

[CustomEditor(typeof(ObjectPlacement))]
public class ObjectPlacementEditor
: Editor

#### **Variables**

#### placementObjectPrefab

private SerializedProperty placementObjectPrefab

#### groundLayer

private SerializedProperty groundLayer

#### obstacleLayer

private SerializedProperty obstacleLayer

#### destructablesLayer

private SerializedProperty destructablesLayer

#### destroyOnPlacement

private SerializedProperty destroyOnPlacement

#### maxDetectionDistance

private SerializedProperty maxDetectionDistance

#### ignoreWhenOverUI

private SerializedProperty ignoreWhenOverUI

#### playerCamera

private SerializedProperty playerCamera

#### rotationSpeed

private SerializedProperty rotationSpeed

#### preserveRotation

private SerializedProperty preserveRotation

#### placementAreaType

private SerializedProperty placementAreaType

#### placementAreaBox

private SerializedProperty placementAreaBox

#### *placementAreaSphere*

private SerializedProperty placementAreaSphere

#### clampInsidePlacementArea

private SerializedProperty clampInsidePlacementArea

#### groundAlignmentType

 $private \ Serialized Property \ ground A lignment Type$ 

#### groundAlignmentDetectionOffset

 $private \ Serialized \textit{Property groundAlignmentDetectionOffset}$ 

#### groundAngleThreshold

private SerializedProperty groundAngleThreshold

#### usePositionSnapping

private SerializedProperty usePositionSnapping

#### gridOrigin

private SerializedProperty gridOrigin

#### gridScale

private SerializedProperty gridScale

#### applyPlacementMaterials

private SerializedProperty applyPlacementMaterials

#### validPlacementMaterials

private SerializedProperty validPlacementMaterials

#### invalidPlacementMaterials

private SerializedProperty invalidPlacementMaterials

#### allowPlacementDuringAnimations

 $private \ Serialized Property \ allow Placement During Animations$ 

#### animatingAngleThreshold

 $private \ Serialized Property \ animating Angle Threshold$ 

#### animatingDistanceThreshold

 $private \ Serialized Property \ animating {\tt DistanceThreshold}$ 

#### animatePositionChange

private SerializedProperty animatePositionChange

#### positionChangeSpeed

private SerializedProperty positionChangeSpeed

#### animateRotationChange

private SerializedProperty animateRotationChange

#### rotationChangeSpeed

private SerializedProperty rotationChangeSpeed

#### gizmoPlacementAreaColor

private SerializedProperty gizmoPlacementAreaColor

#### gizmoPlacementBoundsColor

private SerializedProperty gizmoPlacementBoundsColor

#### gizmoPlacementGroundPositionsColor

 $private \ Serialized {\tt Property} \ gizmoPlace {\tt mentGroundPositionsColor}$ 

#### gizmoGridOriginColor

private SerializedProperty gizmoGridOriginColor

#### gizmoGridPointsColor

private SerializedProperty gizmoGridPointsColor

#### gizmoGridPlacementPointColor

private SerializedProperty gizmoGridPlacementPointColor

#### gizmosGridSphereSize

 $private \ Serialized \textit{Property gizmosGridSphereSize}$ 

#### debugLogsEnabled

private SerializedProperty debugLogsEnabled

#### drawGizmosEnabled

private SerializedProperty drawGizmosEnabled

#### objectPlacement

private ObjectPlacement objectPlacement

#### inputSystemEditor

private Editor inputSystemEditor

#### observerEditor

```
private Editor observerEditor
```

#### prefabsEditor

```
private Editor prefabsEditor
```

#### selectedTabKey

```
private const string selectedTabKey
```

### **Properties**

#### SelectedTabIndex

```
private int SelectedTabIndex
    { set;
    get; }
```

### **Methods**

#### OnEnable

```
private void OnEnable()
```

#### OnDisable

```
private void OnDisable()
```

#### OnInspectorGUI

```
public override void OnInspectorGUI()
```

#### SetupTabGUI

```
private void SetupTabGUI()
```

#### **VisualsTabGUI**

```
private void VisualsTabGUI()
```

#### InputTabGUI

```
private void InputTabGUI()
```

#### PrefabTabsGUI

```
private void PrefabTabsGUI()
```

#### **EventsTabGUI**

```
private void EventsTabGUI()
```

#### RenderPlacementAreaInfo

```
private void RenderPlacementAreaInfo()
```

#### RightAlignedButton

```
private static bool RightAlignedButton(
    string text)
```

#### AddChildObjectComponent

```
private ComponentType AddChildObjectComponent(
    string name)
```

#### DestroyScript

```
private void DestroyScript(
     MonoBehaviour script,
     ref Editor scriptEditor)
```

#### RenderRemoveComponentGUI

```
private void RenderRemoveComponentGUI(
    string buttonText,
    MonoBehaviour script,
    ref Editor customEditor)
```

#### SetDirty

```
private void SetDirty(
    Object target)
```

#### IsObjectInvalid

```
private static bool IsObjectInvalid(
   GameObject go)
```

### APlacementBounds.cs

### **Namespaces**

### TRavljen.PlacementSystem

namespace TRavljen.PlacementSystem

### Classes

#### **APlacementBounds**

```
public abstract class APlacementBounds
: MonoBehaviour, IPlacementBounds
```

Abstract MonoBehaviour for implementing IPlacementBounds. Subclass this component to achieve custom bounds behaviour.

### **Variables**

#### drawGizmo

```
[SerializeField]
private bool drawGizmo
```

### **Properties**

#### PlacementBounds

```
public abstract Bounds PlacementBounds
      { get;
    }
```

#### PlacementRotation

```
public abstract Quaternion PlacementRotation
{ get;
}
```

#### **Methods**

#### OnDrawGizmos

private void OnDrawGizmos()

### ColliderPlacementBounds.cs

### **Namespaces**

### TRavljen.PlacementSystem

namespace TRavljen.PlacementSystem

#### Classes

#### ColliderPlacementBounds

public class ColliderPlacementBounds
: APlacementBounds

Defines placement bounds with use of BoxCollider. When placing an object should consider bounds of a box collider, use this component. It is using manual calculation of the collider bounds because when collider is disabled (for any reason) those bounds (collder.bounds) will be invalid and cannot be used for placement bounds.

### **Variables**

#### placementCollider

```
[Tooltip("Specifies the collider for defining object's placement bounds.")]
[SerializeField]
private BoxCollider placementCollider
```

#### bounds

```
[SerializeField, HideInInspector]
private Bounds bounds
```

### **Methods**

#### PlacementBounds

public override Bounds PlacementBounds()

#### PlacementRotation

public override Quaternion PlacementRotation()

#### **OnValidate**

private void OnValidate()

#### **UpdateBounds**

private void UpdateBounds()

#### SetCollider

### **CustomPlacementBounds.cs**

### **Namespaces**

### TRavljen.PlacementSystem

namespace TRavljen.PlacementSystem

#### Classes

#### CustomPlacementBounds

public class CustomPlacementBounds
: APlacementBounds

Defines custom bounds for the game object, which is required for placing an object using ObjectPlacement.

#### **Variables**

#### center

```
[Tooltip("Specifies center (offset) of the custom bounds in local space.")]
public Vector3 center
```

#### size

```
[Tooltip("Specifies size of the custom bounds.")]
public Vector3 size
```

#### \_transform

```
private Transform _transform
```

### **Methods**

#### PlacementBounds

```
public override Bounds PlacementBounds()
```

#### PlacementRotation

```
public override Quaternion PlacementRotation()
```

#### Awake

```
private void Awake()
```

#### OnValidate

```
private void OnValidate()
```

### IPlacementBounds.cs

### **Namespaces**

### TRavljen.PlacementSystem

```
namespace TRavljen.PlacementSystem
```

#### Classes

#### *IPlacementBounds*

```
public interface IPlacementBounds
```

Interface for providing placement bounds for a placing object.

### **Properties**

#### gameObject

```
public GameObject gameObject
    { get;
    }
```

Root game object of the placing object.

#### **PlacementBounds**

```
public Bounds PlacementBounds
{ get;
}
```

Bounds relative to local position of the root gameObject.

#### PlacementRotation

```
public Quaternion PlacementRotation
    { get;
}
```

Absolute rotation of the placing object.

### RendererPlacementBounds.cs

### **Namespaces**

### TRavljen.PlacementSystem

namespace TRavljen.PlacementSystem

#### **Classes**

#### RendererPlacementBounds

```
public class RendererPlacementBounds
: APlacementBounds
```

Defines placement bounds with use of Renderer. When placing an object should consider bounds of a renderer, use this component.

#### **Variables**

#### \_renderer

```
[Tooltip("Specifies the renderer used to extract bounds from")]
[SerializeField]
private Renderer _renderer
```

#### **Methods**

#### **PlacementBounds**

```
public override Bounds PlacementBounds()
```

#### PlacementRotation

```
public override Quaternion PlacementRotation()
```

#### SetRenderer

```
public void SetRenderer(
    Renderer renderer)
```

Sets new renderer for placement bounds. Null should not be passed, instead disable or destroy this component.

renderer: New renderer

### Input

### AlnputControl.cs

### **Namespaces**

### TRavljen.PlacementSystem

namespace TRavljen.PlacementSystem

#### Classes

#### **AInputControl**

```
[System.Serializable]
public abstract class AInputControl
: MonoBehaviour
```

Abstract class for defining player's interface with placement system. It is intendede that this component listens to player input for specific input packages, while InputControlResponder handles interactions with the system.

### **Properties**

#### OnPlacementCancel

```
public UnityEvent OnPlacementCancel
      { get;
      set; }
```

Invoke this when action for canceling selection was triggered.

#### OnPlacementActiveToggle

```
public UnityEvent OnPlacementActiveToggle
    { get;
    set; }
```

Invoke this once mouse down action is true (mouse click).

#### OnPlacementFinish

```
public UnityEvent OnPlacementFinish
      { get;
      set; }
```

Invoke this once mouse up action is true (mouse released).

#### OnRotate

```
public UnityEvent<float> OnRotate
    { get;
    set; }
```

Invoke this with direction and magnitude of the rotation, positive is clockwise and negative is counter clockwise.

#### OnNextPrefab

```
public UnityEvent OnNextPrefab
{ get;
set; }
```

Invoke this when placement prefab should be changed to the next one.

#### OnPreviousPrefab

```
public UnityEvent OnPreviousPrefab
    { get;
    set; }
```

Invoke this when placement prefab should be changed to the previous one.

#### OnPrefabAction

```
public UnityEvent<int> OnPrefabAction
    { get;
    set; }
```

Invoke this when placement prefab should be changed for one on specific index.

### **ActionInputControl.cs**

### **Namespaces**

### TRavljen.PlacementSystem

```
namespace TRavljen.PlacementSystem
```

#### Classes

### ActionInputControlEditor

```
[CustomEditor(typeof(ActionInputControl))]
public class ActionInputControlEditor
: HiddenScriptPropertyEditor
```

#### ActionInputControl

```
public class ActionInputControl
: AInputControl, ICursorPositionProvider
```

Behaviour component for defining players input by using Unity's new UnityEngine.InputSystem. This component is only available when the package for New Input system is in the project.

#### **Enumerations**

### CursorPositionType

```
enum CursorPositionType{
    Mouse,
    TouchScreen}
```

Mouse: Uses current position of the mouse cursor.

TouchScreen: Uses current touch position on screen.

#### **Variables**

#### cancelAction

```
[Header("General")]
[Tooltip("Specifies the action used for canceling active placement.")]
[Space]
public InputAction cancelAction
```

#### toggleActivePlacementAction

```
[Space]
[Tooltip("Specifies the action for starting placement process with " +
"currently selected game object prefab.")]
public InputAction toggleActivePlacementAction
```

#### finishPlacementAction

```
[Space]
[Tooltip("Specifies the action for finishing placement process" +
"(placing object in world).")]
public InputAction finishPlacementAction
```

#### rotateClockwiseAction

```
[Header("Rotation")]
[Space]
[Tooltip("Specifies the clockwise rotation input action. You can change " +
"rotation behaviour from <b>Press</b> to <b>Hold</b>
by changing the " +
"Action Type from <b>Button</b> to
<b>Passthrough</b> or <b>Value</b>.")]
public InputAction rotateClockwiseAction
```

#### rotateCounterClockwiseAction

```
[SerializeField, Space]
[Tooltip("Specifies the counter clockwise rotation input action.
" +
"You can change rotation behaviour from <b>Press</b>
to <b>Hold</b> by " +
"changing the Action Type from <b>Button</b> to
<b>Passthrough</b> or " +
"<b>Value</b>.")]
public InputAction rotateCounterClockwiseAction
```

#### nextPrefabAction

```
[Header("Prefab Control")]
[Space]
public InputAction nextPrefabAction
```

#### previousPrefabAction

```
public InputAction previousPrefabAction
```

#### prefabActions

```
[Space]
public InputAction[] prefabActions
```

#### *cursorPositionType*

```
[Tooltip("Specifies the type of cursor position behaviour. By default " +
  "mouse position is read, alternatively touch screen position can be " +
  "used for mobile devices and such.")]
  [SerializeField, Header("Cursor")]
  private CursorPositionType cursorPositionType
```

#### \_cursorPositionType

```
[SerializeField, HideInInspector]
private CursorPositionType _cursorPositionType
```

#### cursorPositionAction

```
[Tooltip("Specifies the cursor position. Most commonly this would be " + "mouse position or touch screen position.

Alternatively custom one " + "can be added for others like controller sticks.")]

[Space]

public InputAction cursorPositionAction
```

#### \_initialSetup

```
[SerializeField, HideInInspector]
private bool _initialSetup
```

### **Properties**

#### CursorPosition

```
public Vector3 CursorPosition
    { get;
    }
```

#### **Methods**

#### OnEnable

```
private void OnEnable()
```

#### OnDisable

```
private void OnDisable()
```

#### Start

```
private void Start()
```

#### Update

```
private void Update()
```

#### OnValidate

```
private void OnValidate()
```

#### OnDestroy

private void OnDestroy()

#### **HandleCancelAction**

#### **HandleToggleActivePlacementAction**

#### HandleFinishPlacementAction

#### **HandleClockwiseRotation**

#### HandleCounterClockwiseRotation

#### **HandleNextPrefabAction**

#### **HandlePreviousPrefabAction**

#### **HandlePrefabAction**

#### InitialSetupIfNeeded

private void InitialSetupIfNeeded()

#### SetupCursorAction

private void SetupCursorAction()

#### **IsPressed**

#### **IsPressed**

### InputControlResponder.cs

### **Namespaces**

### TRavljen.PlacementSystem

namespace TRavljen.PlacementSystem

### Classes

### InputControlResponder

internal sealed class InputControlResponder
: MonoBehaviour

Responder class for invoking methods on ObjectPlacement based on AlnputControl component events which must be attached to the same game object.

#### **Variables**

#### placement

private ObjectPlacement placement

#### **Methods**

#### Awake

private void Awake()

#### OnEnable

private void OnEnable()

#### OnDisable

private void OnDisable()

#### **AddListeners**

private void AddListeners()

#### RemoveListeners

private void RemoveListeners()

### ToggleActivePlacement

private void ToggleActivePlacement()

#### CancelPlacement

private void CancelPlacement()

### **EndPlacement**

private void EndPlacement()

#### RotatePlacement

private void RotatePlacement(
 float directionalMagnitude)

# KeyInputControl.cs

# **Namespaces**

# TRavljen.PlacementSystem

namespace TRavljen.PlacementSystem

# *KeyInputControlEditor*

```
[CustomEditor(typeof(KeyInputControl))]
public class KeyInputControlEditor
: HiddenScriptPropertyEditor
```

## *KeyInputControl*

```
[System.Serializable]
public class KeyInputControl
: AInputControl
```

Behaviour component for defining players input by using Unity's OLD Input.

## **Variables**

### toggleActivePlacementKey

```
[Header("General")]
[Tooltip("Specifies the key for starting placement process with
" +
"currently selected game object prefab.")]
public KeyCode toggleActivePlacementKey
```

#### cancelPlacementKey

```
[Tooltip("Specifies the key used for canceling active placement.")]
public KeyCode cancelPlacementKey
```

#### finishPlacementKey

```
[Tooltip("Specifies the key for finishing placement process " + "(placing object in world).")]
public KeyCode finishPlacementKey
```

#### holdToRotate

```
[Header("Rotation")]
[Tooltip("Specifies if rotation should be applied on key hold or key press.")]
public bool holdToRotate
```

### rotateClockwiseKey

```
[Tooltip("Specifies the clockwise rotation input key.")]
public KeyCode rotateClockwiseKey
```

### rotateCounterClockwiseKey

[Tooltip("Specifies the counter clockwise rotation input key.")] public KeyCode rotateCounterClockwiseKey

#### nextPrefabKey

public KeyCode nextPrefabKey

### previousPrefabKey

public KeyCode previousPrefabKey

### prefabKeys

public KeyCode[] prefabKeys

# Cursor

# **DefaultMousePositionProvider.cs**

## **Namespaces**

## TRavljen.PlacementSystem

namespace TRavljen.PlacementSystem

### Classes

### DefaultMousePositionProvider

sealed class DefaultMousePositionProvider
: ICursorPositionProvider

Internal implementation for default mouse position behaviour. ActionInputControl implements the ICursorPositionProvider to add touch screen support.

# **Properties**

#### CursorPosition

```
public Vector3 CursorPosition
    { get;
    }
```

# ICursorPositionProvider.cs

# **Namespaces**

# TRavljen.PlacementSystem

namespace TRavljen.PlacementSystem

### Classes

## *ICursorPositionProvider*

```
public interface ICursorPositionProvider
```

Interface for implementing a custom cursor position handling. It can be used for mouse, touch screen and even controller sticks.

# **Properties**

#### CursorPosition

```
public Vector3 CursorPosition
    { get;
    }
```

Current cursor position, most commonly this would be current mouse position.

# Interface

# IPlacingObject.cs

# **Namespaces**

# TRavljen.PlacementSystem

namespace TRavljen.PlacementSystem

# IPlacingObject

```
public interface IPlacingObject
```

Interface for notifying a specific game object of its placement status. Implement this interface by subclassing a MonoBehaviour component and then update your game object with custom behaviour upon these events.

### **Methods**

#### **PlacementStarted**

```
public void PlacementStarted()
```

Invoked when placement on this object has started. In such case the object is a template instance created for active placement only.

#### PlacementValidated

```
public void PlacementValidated(
          bool isValid)
```

Invoked when placement on this object is validated.

isValid: If placement of the object is valid at this moment.

#### **PlacementEnded**

```
public void PlacementEnded()
```

Invoked when placement of this object is finished. This will be invoked on final instance created when placement is complete.

#### **PlacementFailed**

```
public void PlacementFailed()
```

Invoked when placement of this object has failed. This happens when placement is attempted with invalid position and rotation.

#### PlacementCancelled

```
public void PlacementCancelled()
```

Invoked when placement of this object is cancelled.

# IValidatePlacement.cs

# **Namespaces**

# TRavljen.PlacementSystem

namespace TRavljen.PlacementSystem

### Classes

### *IValidatePlacement*

public interface IValidatePlacement

Interface for additional custom validation for object's placement. You can implement this to verify if certain objects can be placed in certain locations, under specific rotation.

## **Methods**

#### IsPlacementValid

public bool IsPlacementValid(
 GameObject gameObject,
 Bounds bounds,
 Quaternion rotation)

Validates placement of a game object.

gameObject: Game object to validate bounds: Bounds of the game object rotation: Rotation of bounds in world space

Returns: Returns true if object has been validated and can be placed, returns false when it cannot be placed.

# ObjectPlacementEvents.cs

# Namespaces

# TRavljen.PlacementSystem

namespace TRavljen.PlacementSystem

# ObjectPlacementEvents

sealed public class ObjectPlacementEvents

Class holding references to public events invoked when placement system is active, respectively.

### **Variables**

#### Instance

public static readonly ObjectPlacementEvents Instance

#### OnPlacementStart

public readonly UnityEvent<GameObject> OnPlacementStart

Event invoked when placement has started, receiving the object instance created for placement.

#### OnPlacementValidate

public readonly UnityEvent<bool> OnPlacementValidate

Event invoked when placement of an object is finished validating.

#### OnPlacementEnd

public readonly UnityEvent<GameObject,PlacementResult>
OnPlacementEnd

Event invoked when placement has ended successfully, receiving the new game object instance and the result of placement. In case ObjectPlacement. TryEndPlacement(out PlacementResult) is invoked, then the new object received will be null.

#### OnPlacementFail

public readonly UnityEvent OnPlacementFail

Event invoked when placement has been attempted, placement validation prevented the placement.

#### OnPlacementCancel

public readonly UnityEvent OnPlacementCancel

Event invoked when an active placement has been canceled.

### OnObjectDestroy

public readonly UnityEvent<GameObject> OnObjectDestroy

Event invoked when an object will or should be destroyed. Depending on placement configuration.

# ObjectPlacementObserver.cs

# **Namespaces**

## TRavljen.PlacementSystem

namespace TRavljen.PlacementSystem

### **Classes**

## ObjectPlacementObserverEditor

[CustomEditor(typeof(ObjectPlacementObserver))]
public class ObjectPlacementObserverEditor
: HiddenScriptPropertyEditor

# ObjectPlacementObserver

public class ObjectPlacementObserver
: MonoBehaviour

MonoBehaviour component used for observing all the events on ObjectChangeEvents and expose them in Unity Editor. This is a convenience script that can be used in Editor instead of adding listeners through the code.

## **Variables**

#### OnPlacementStart

[Tooltip("Event invoked when placement has begun, receiving the object instance created for placement.")]
public UnityEvent<GameObject> OnPlacementStart

#### OnPlacementValidate

[Tooltip("Event invoked when placement of an object is finished validating.")]
public UnityEvent<bool> OnPlacementValidate

#### OnPlacementEnd

```
[Tooltip("Event invoked when placement has ended successfully, receiving the new game object instance and the result of placement.\n" +
"In case 'ObjectPlacement.TryEndPlacement(out
PlacementResult)' is invoked, then the new object received will be null.")]
public UnityEvent<GameObject,PlacementResult> OnPlacementEnd
```

#### OnPlacementFail

```
[Tooltip("Event invoked when placement has been attempted, placement validation prevented the placement.")]
public UnityEvent OnPlacementFail
```

#### OnPlacementCancel

```
[Tooltip("Event invoked when an active placement has been canceled.")]
public UnityEvent OnPlacementCancel
```

#### OnObjectDestroy

```
[Tooltip("Event invoked when an object will or should be destroyed. Depending on placement configuration.")]
public UnityEvent<GameObject> OnObjectDestroy
```

#### events

```
private ObjectPlacementEvents events
```

## **Methods**

#### OnEnable

```
private void OnEnable()
```

#### **OnDisable**

```
private void OnDisable()
```

# PlacementPrefabs.cs

# **Namespaces**

# TRavljen.PlacementSystem

namespace TRavljen.PlacementSystem

### Classes

## PlacementPrefabs

```
public class PlacementPrefabs
: MonoBehaviour
```

Manages the selection and placement of prefabs within the scene. This class handles cycling through a list of prefabs and updating the active prefab for placement.

## **Variables**

### prefabs

```
[Tooltip("Array of prefabs that can be cycled through for placement.")]
[SerializeField]
private GameObject[] prefabs
```

### cyclesRotation

```
[Tooltip("Specifies whether the prefab selection will cycle (wrap around) when reaching the start or end of the list.")]
[SerializeField]
private bool cyclesRotation
```

#### index

```
private int index
```

Index of the currently selected prefab.

## **Methods**

#### Prefabs

```
public GameObject[] Prefabs()
```

Gets the array of prefabs that can be selected for placement.

#### Start

```
private void Start()
```

Initializes the component by setting up the input control listeners.

#### SetPrefabs

```
public void SetPrefabs(
   GameObject[] prefabs)
```

Sets the array of prefabs that can be selected for placement.

prefabs: Array of prefabs to assign.

#### Next

```
public void Next()
```

Selects the next prefab in the array. If cycling is enabled, wraps around to the first prefab.

#### Back

```
public void Back()
```

Selects the previous prefab in the array. If cycling is enabled, wraps around to the last prefab.

#### SetPrefabIndex

```
public void SetPrefabIndex(
    int index)
```

Sets the prefab index to the specified value if within valid range.

index: The index of the prefab to select.

### ClampIndex

```
private int ClampIndex(
   int newIndex)
```

Clamps the index to ensure it remains within the valid range, optionally cycling if enabled.

newIndex: The new index to clamp.

Returns: The clamped index.

### **UpdateIndex**

```
private void UpdateIndex(
    int newIndex)
```

Updates the index of the selected prefab and sets the active placement prefab in the ObjectPlacement system.

newIndex: The new index to set.

# PlacementPrefabsEditor.cs

# **Namespaces**

# TRavljen.PlacementSystem

namespace TRavljen.PlacementSystem

### Classes

### PlacementPrefabsEditor

[CustomEditor(typeof(PlacementPrefabs))]
class PlacementPrefabsEditor
: UnityEditor.Editor

### **Variables**

### prefabs

 $Serialized Property\ prefabs$ 

#### cyclesRotation

SerializedProperty cyclesRotation

### **Methods**

#### OnEnable

private void OnEnable()

public override void OnInspectorGUI()

# PlacementResult.cs

# **Namespaces**

# TRavljen.PlacementSystem

namespace TRavljen.PlacementSystem

### Classes

### PlacementResult

public struct PlacementResult

Information about the placement result. It contains objects placing position and it's rotation.

# **Variables**

#### Position

public Vector3 Position

Position of the placement.

#### Rotation

public Quaternion Rotation

Rotation of the placement.

# PlacingObjectObserver.cs

# **Namespaces**

# TRavljen.PlacementSystem

namespace TRavljen.PlacementSystem

## PlacingObjectObserver

```
public class PlacingObjectObserver
: MonoBehaviour, IPlacingObject
```

Observer component that implements IPlacingObject and supports referencing events within the Unity Editor. This is for cases where a simple action needs to be performed based on an event to avoid implementing a custom IPlacingObject MonoBehaviour.

### **Variables**

### OnPlacementStart

```
[Tooltip("Invoked when placement on this object has started. " +

"In such case the object is a template instance
created for active placement only.")]

public UnityEvent OnPlacementStart
```

#### OnPlacementValidated

```
[Tooltip("Invoked when placement on this object is validated.\n" +
"Value passed is true if placement of the object is valid at this moment.")]
public UnityEvent<bool> OnPlacementValidated
```

#### OnPlacementEnd

```
[Tooltip("Invoked when placement of this object is finished." +

"This will be invoked on final instance created when
placement is complete.")]
public UnityEvent OnPlacementEnd
```

#### OnPlacementCancel

```
[Tooltip("Invoked when placement of this object is cancelled.")] public UnityEvent OnPlacementCancel
```

#### OnPlacementFail

```
[Tooltip("Invoked when placement of this object has failed." + "This happens when placement is attempted with invalid position and rotation.")]
public UnityEvent OnPlacementFail
```

### **Methods**

#### **PlacementStarted**

public void PlacementStarted()

#### **PlacementValidated**

public void PlacementValidated(
 bool isValid)

#### PlacementEnded

public void PlacementEnded()

#### PlacementCancelled

public void PlacementCancelled()

#### PlacementFailed

public void PlacementFailed()

# **PlacementArea**

# ASpherePlacementAreas.cs

# **Namespaces**

# TRavljen.PlacementSystem

namespace TRavljen.PlacementSystem

### Classes

# **ASpherePlacementAreas**

[RequireComponent(typeof(ObjectPlacement))]
public abstract class ASpherePlacementAreas
: MonoBehaviour, IPlacementArea

### **Variables**

#### placement

```
[HideInInspector]
[SerializeField]
protected ObjectPlacement placement
```

### overrideType

```
[Tooltip("Specifies if the boundsType should be overridden.
Leave this disabled and " +
"manually control the type of the placement
area.")]
[SerializeField]
protected bool overrideType
```

### gizmosColor

```
[Header("Preview")]
[SerializeField]
protected Color gizmosColor
```

### alwaysShowGizmos

```
[SerializeField]
protected bool alwaysShowGizmos
```

### **Methods**

#### **GetAreas**

```
protected abstract SphereBounds[] GetAreas()
```

#### Awake

```
protected virtual void Awake()
```

#### OnValidate

```
protected virtual void OnValidate()
```

#### IPlacementArea.ClosestPosition

```
Vector3 IPlacementArea.ClosestPosition(
Vector3 position)
```

#### IPlacementArea.IsInside

#### **OnDrawGizmos**

protected virtual void OnDrawGizmos()

# IPlacementArea.cs

# **Namespaces**

# TRavljen.PlacementSystem

namespace TRavljen.PlacementSystem

## Classes

### *IPlacementArea*

public interface IPlacementArea

Defines contract for a placement area.

# **Methods**

#### ClosestPosition

Returns closest position within the area.

### IsInside

Checks whether the position is inside the area.

# ObjectPlacementArea.cs

# **Namespaces**

# TRavljen.PlacementSystem

namespace TRavljen.PlacementSystem

### Classes

## ObjectPlacementAreaEditor

```
[CustomEditor(typeof(ObjectPlacementArea), true)]
public sealed class ObjectPlacementAreaEditor
: HiddenScriptPropertyEditor
```

## **Methods**

### OnInspectorGUI

public override void OnInspectorGUI()

## ObjectPlacementArea

```
[DisallowMultipleComponent]
public class ObjectPlacementArea
: MonoBehaviour
```

Component which specifies a valid placement area for a game object. This component manages adding and removing placement are on ObjectPlacementAreaManager when enabled or disabled. To manage when placement area is added, simply enable and disable this component.

### **Variables**

#### areaBounds

```
[Tooltip("Specifies area bounds provided by the game object.
Position is relative.")]
[SerializeField]
private SphereBounds areaBounds
```

#### gizmoColor

```
[Header("Preview")]
[SerializeField]
private Color gizmoColor
```

#### disableGizmo

```
[SerializeField]
private bool disableGizmo
```

# **Properties**

#### WorldBounds

```
public SphereBounds WorldBounds
    { get;
    }
```

## **Methods**

#### Start

```
private void Start()
```

#### OnEnable

```
private void OnEnable()
```

#### OnDisable ( )

```
private void OnDisable()
```

### **TryGetManager**

```
private bool TryGetManager(
   out ObjectPlacementAreaManager manager)
```

#### OnDrawGizmos

```
private void OnDrawGizmos()
```

# ObjectPlacementAreaManager.cs

# **Namespaces**

# TRavljen.PlacementSystem

```
namespace TRavljen.PlacementSystem
```

# ObjectPlacementAreaManagerEditor

[CustomEditor(typeof(ObjectPlacementAreaManager), true)]
class ObjectPlacementAreaManagerEditor
: UnityEditor.Editor

## **Methods**

## OnInspectorGUI

public override void OnInspectorGUI()

# ObjectPlacementAreaManager

public class ObjectPlacementAreaManager
: ASpherePlacementAreas

Component which manages a list of objects and their placement areas.

## **Variables**

### \_objectAreas

private readonly Dictionary<GameObject,SphereBounds>
\_objectAreas

#### areas

private SphereBounds[] areas

### **Methods**

#### **GetAreas**

protected override SphereBounds[] GetAreas()

#### Awake

protected override void Awake()

### Add0bjectArea

public void AddObjectArea(
 GameObject obj,
 Vector3 position,
 float radius)

Add area for the game object.

obj: Area game object owner position: Center world position.

radius: Radius

### RemoveObjectArea

Remove area for the game object.

obj: Area game object owner.

#### OnDrawGizmos

protected override void OnDrawGizmos()

# PlacementAreaInfo.cs

# **Namespaces**

# TRavljen.PlacementSystem

namespace TRavljen.PlacementSystem

## **Enumerations**

## PlacementAreaType

```
public enum PlacementAreaType{
   Anywhere,
   Box,
   Sphere,
   Custom}
```

Type of the bounds in which the objects can be placed.

Anywhere: Objects can be placed anywhere where there is ground.

Box: Objects can be placed on ground within the box bounds of the area.

Sphere: Objects can be placed on ground in the sphere bounds of the area.

Custom: Placement area defined by a custom implementation by implementing IPlacementArea interface.

### Classes

### PlacementAreaInfo

```
[Serializable]

public struct PlacementAreaInfo

: IPlacementArea
```

Specifies the information about valid placement area for objects. When placement area is limited, use ClosestPosition to limit the positions within the valid bounds.

## **Variables**

#### boundsType

```
[Tooltip("Specifies placement area type. In cases where map has a limit or " + "placement is allowed around certain objects use this to limit " + "the placement area.")]
public PlacementAreaType boundsType
```

#### boxBounds

```
[Tooltip("Specifies placement area with box shape. Set it's position and size.")]
public Bounds boxBounds
```

#### sphereBounds

```
[Tooltip("Specifies placement area with sphere shape. Set it's position and size.")]
public SphereBounds sphereBounds
```

#### customArea

```
public IPlacementArea customArea
```

Specifies custom placement area component. This allows easy use of multiple placement areas with custom implementation.

### **Methods**

#### ClosestPosition

Clamps position within the valid placement area. For PlacementAreaType.Anywhere the same value will be returned, for limiting types the closest position within the bounds will be found.

position: Current position

Returns: Valid position

#### IsInside

#### RenderGizmos

Renders gizmo for current placement area.

areaColor: Color for area gizmo.

# SpherePlacementAreaManager.cs

# **Namespaces**

# TRavljen.PlacementSystem

namespace TRavljen.PlacementSystem

## SpherePlacementAreaManager

```
public class SpherePlacementAreaManager
: ASpherePlacementAreas
```

Component which manages a list of areas of type sphere/ring. You can add or remove them dynamically in runtime.

## **Variables**

#### areas

```
[Tooltip("Specifies ring areas for valid placements. At least one must be present!")]
[SerializeField]
protected SphereBounds[] areas
```

# **Utility**

# ColliderBoundsHelper.cs

# **Namespaces**

# TRavljen.PlacementSystem.Utility

 $name space \ TRavljen. Placement System. Utility$ 

### Classes

# ColliderBoundsHelper

static public class ColliderBoundsHelper

### **Methods**

#### CalculateBounds

Retrieving collider bounds while the collider itself is disabled will return Vector3 of zero size. This method will calculate it from collider center and size, while applying its transform's rotation and scale. The bounds position is still in local space.

collider: Collider to calculate the Bounds for

# GridSnapper.cs

# **Namespaces**

# TRavljen.PlacementSystem.Utility

namespace TRavljen.PlacementSystem.Utility

## Classes

## GridSnapper

[System.Serializable] sealed public class GridSnapper

## **Constructors**

#### GridSnapper

Creates a grid of specified origin and size.

### **Variables**

### gridScale

```
[SerializeField]
[Tooltip("Specifies the grid size (space between snapping points).")]
private Vector2 gridScale
```

### grid0rigin

```
[SerializeField]
[Tooltip("Specifies the origin of the snapping grid. Y axis is not used.")]
private Vector3 gridOrigin
```

### gizmoGridOriginColor

```
[SerializeField]
[Tooltip("Specifies the color of the grid origin sphere gizmo.")]
private Color gizmoGridOriginColor
```

### gizmoGridPointsColor

```
[SerializeField]
[Tooltip("Specifies the color of the grid point spheres gizmo.")]
private Color gizmoGridPointsColor
```

### gizmoGridPlacementPointColor

```
[SerializeField]
[Tooltip("Specifies the point of placement on the grid. " +
"Grid gizmos will follow this point to avoid
rendering too many.")]
private Color gizmoGridPlacementPointColor
```

### gizmosSphereSize

```
[SerializeField]
[Range(0.1F, 10F)]
[Tooltip("Specifies the sphere size for grid points.")]
private float gizmosSphereSize
```

#### MaxCellRowCount

```
private const float MaxCellRowCount
```

Max cell count for single row/column. If changed, this should always remain an even number.

#### lastNereastPoint

```
private Vector3 lastNereastPoint
```

Specifies the last point on grid that was calculated. Vector3.zero is the default value.

# **Properties**

### ClearOrigin

```
private Vector3 ClearOrigin
    { get;
}
```

Clears Y axis from origin.

# **Methods**

### RenderDebugPoints

```
public void RenderDebugPoints()
```

Renders spheres of the grid points, used for snapping.

#### **Validate**

```
public void Validate()
```

Validates and clamps the gridScale.

#### SnapToGrid

```
public Vector3 SnapToGrid(
    Vector3 position)
```

Snaps a position to the nearest grid point.

# **GroundPlacement.cs**

# **Namespaces**

# TRavljen.PlacementSystem.Utility

namespace TRavljen.PlacementSystem.Utility

# GroundAlignment

```
[System.Serializable]
class GroundAlignment
```

Finds ground bottom points of the rotated bounds in world space and if needed, aligns the bounds to ground with new position and rotation.

## **Constructors**

### GroundAlignment

```
public GroundAlignment()
```

## **Variables**

#### GroundDetectionOffset

```
[HideInInspector]
[Range(-150, 150)]
[Tooltip("Specifies the Y offset of raycast detection for ground position. " +
"Detected points on bounds edges define the angle of object placement.")]
public float GroundDetectionOffset
```

#### debugLogsEnabled

```
public bool debugLogsEnabled
```

#### bottomPoints

```
private Vector3[] bottomPoints
```

#### hit

```
private RaycastHit hit
```

### **Methods**

#### **BottomPoints**

```
public Vector3[] BottomPoints()
```

#### ${f Try}{f GetAligned}{f Position}{f With}{f Ground}$

```
public bool TryGetAlignedPositionWithGround(
    Bounds bounds,
    Quaternion currentRotation,
    LayerMask groundLayer,
    out Quaternion newRotation,
    out Vector3 newPosition)
```

Attempts to find the new position and rotation for the placing bounds.

bounds: Bounds of placing object

currentRotation: Rotation of bounds in world space

groundLayer: Layer of ground to detect placement colliders (mesh or terrain).

newRotation: New rotation in world space, aligned to ground newPosition: New position in world space, positioned on ground

Returns: Returns true if alignment was successful, returns false if it was not

#### FindGroundPoints

```
public bool FindGroundPoints(
    Bounds bounds,
    Quaternion rotation,
    LayerMask groundLayer,
    ref Vector3[] points)
```

Takes the bottom 4 edges of the rotated bounds and finds the nearest ground below it using Physics.Raycast(Vector3, Vector3, out RaycastHit, float, int).

bounds: Bounds of placing object

rotation: Rotation of bounds in world space

groundLayer: Layer of ground to detect placement colliders (mesh or terrain).

points: Points updated if ground was found

Returns: Returns true if ground for all 4 edges was found.

#### CalculatePlaneNormal

```
static Vector3 CalculatePlaneNormal(
Vector3[] points)
```

Calculates planes normal vector.

#### **GetBottomEdges**

```
static void GetBottomEdges(
Vector3 center,
Vector3 size,
Quaternion rotation,
ref Vector3[] edges)
```

Calculates the bottom edges of a bounding box in world space.

# InstantiatePlacementObject.cs

# **Namespaces**

# TRavljen.PlacementSystem

namespace TRavljen.PlacementSystem

### Classes

# InstantiatePlacementObject

public static class InstantiatePlacementObject

Helper methods for instantiatin a new object template used for visual placement.

## **Methods**

#### **TryInstantiate**

```
public static GameObject TryInstantiate(
   GameObject prefab,
   Vector3 position,
   Quaternion rotation,
   Transform parent,
   out IPlacementBounds bounds)
```

### **TryCreatePlacementBounds**

public static bool TryCreatePlacementBounds(
 GameObject newInstance,
 out IPlacementBounds placementBounds)

# IntRange.cs

# **Namespaces**

# TRavljen.Utility

namespace TRavljen.Utility

### IntRange

```
[System.Serializable]
public struct IntRange
```

Specifies an integer range by defining its lower and upper bounds with min and max values.

## **Constructors**

### IntRange

```
public IntRange(
   int min,
   int max)
```

## **Variables**

#### min

```
public int min
```

Minimal/lower bound of the integer range.

#### max

```
public int max
```

Maximal/upper bound of the integer range.

## **Methods**

#### Clamp

```
public float Clamp(
  float value)
```

Clamps the value within the range.

value: Value to clamp

Returns: Returns a value within the Integer range

#### *IsWithinBounds*

```
public bool IsWithinBounds(
float value)
```

Checks if the value is within the integer range/bounds. Min and max values are inclusive.

value: Value to check

Returns: Returns true if the value is within integer range.

# IntRangeAttribute.cs

# **Namespaces**

# TRavljen. Utility

namespace TRavljen.Utility

## **Classes**

# IntRangeAttribute

```
public class IntRangeAttribute
: PropertyAttribute
```

## **Constructors**

## IntRangeAttribute

```
public IntRangeAttribute(
  int min,
  int max)
```

# **Properties**

#### Min

```
public int Min
{ get;
}
```

#### Max

```
public int Max
{ get;
}
```

# TRavljen. Utility

```
namespace TRavljen.Utility
```

## **Classes**

## IntRangeAttributeDrawer

```
[CustomPropertyDrawer(typeof(IntRangeAttribute))]
public class IntRangeAttributeDrawer
: PropertyDrawer
```

## **Methods**

#### **OnGUI**

```
public override void OnGUI(
    Rect position,
    SerializedProperty property,
    GUIContent label)
```

# MathHelper.cs

# **Namespaces**

# TRavljen.PlacementSystem.Utility

```
namespace TRavljen.PlacementSystem.Utility
```

## **Classes**

## MathHelper

static class MathHelper

## **Methods**

### AngleDistance

```
public static float AngleDistance(
   float angle1,
   float angle2)
```

Calculates the distance between two angles.

#### WrapAngle

```
public static float WrapAngle(
   float angle)
```

Wraps the angle within a valid range for calculation (euler). This means the returned value will be within -180 and 180 range by modifying the value as required (+/- 360).

# SphereBounds.cs

# **Namespaces**

# TRavljen.PlacementSystem

namespace TRavljen.PlacementSystem

### Classes

# SphereBounds

```
[System.Serializable]
public struct SphereBounds
```

Defines bounds of a sphere with center and radius.

## **Constructors**

#### SphereBounds

```
public SphereBounds(
    Vector3 center,
    float radius)
```

## **Variables**

#### center

```
[Tooltip("Specifies bounds center.")]
public Vector3 center
```

#### radius

```
[Tooltip("Specifies bounds radius.")]
[Range(0.01f, 200f)]
public float radius
```

## **Methods**

#### Contains

```
public bool Contains(
Vector3 point)
```

Checks if a point is within the sphere.

#### Intersects

```
public bool Intersects(
SphereBounds other)
```

Checks if another sphere intersects with this sphere.

#### ToBounds

```
public Bounds ToBounds()
```

Get a bounding box that contains this sphere

#### ClosestPoint

```
public Vector3 ClosestPoint(
    Vector3 point)
```

Finds the closest point on the sphere surface to the given point.