


Cyber Operational Resilience Decision Intelligence

Explain service dependencies, control planes and trusted recovery design

HARBOR RIDGE BANK | FICTIONAL DEMONSTRATION CLIENT


Critical services must be traced through authority and recovery

Technical design starts with service tolerance, not infrastructure inventory.



Enterprise identity holds the broadest declared authority

Seven critical relationships make identity the leading modeled concentration.



Identity is the largest modeled common-mode concentration. The count is evidence of dependency, not likelihood or loss.

Tier 0 dependencies require evidence-backed ownership

Broad authority, multi-service effect and trusted recovery determine candidacy.

- Identity and privileged access
- DNS, certificates and time
- Network, cloud, virtualization and database management
- Backup and recovery orchestration

Shared identity and administration can defeat component redundancy

Redundant applications remain exposed when the same authority controls both paths.

Component redundancy is not control-plane independence.

Test administrative separation and break-glass authority.

A deployed tool is not the same as tested coverage

Coverage progresses through configuration, telemetry, detection testing, response integration and recovery visibility.

Independent Tier 0 recovery

UNVALIDATED

Owner + evidence + trend

Privilege-disable decision time

MEASURE

Owner + evidence + trend

Unreconciled transactions

MONITOR

Owner + evidence + trend

Third-party substitution

TEST

Owner + evidence + trend

Recovery design must separate availability from trust

Journal, ledger and reconciliation evidence determine whether restored service is safe.

KEEP CHANNEL OPEN

Preserves access

May increase unreconciled transactions and customer harm if data cannot be trusted

SUSPEND CHANNEL

Limits questionable posting

Creates immediate service disruption and manual-processing pressure

Decision evidence: journal integrity, independent reconciliation, customer harm and settlement obligations

Production control planes remain implicit recovery prerequisites

The current state can reproduce compromised authority or corrupted data.

CURRENT

Production identity

Production DNS

Replicated data

Shared monitoring



TARGET

Independent recovery identity

Independent name resolution

Offline integrity evidence

Recovery-visible telemetry

Clean authority must precede data restoration

Independent DNS, offline evidence and recovery telemetry support trusted service restoration.

0-90 DAYS

Approve Tier 0
Freeze unmanaged privilege
Validate clean credentials

NEXT 2 QUARTERS

Independent recovery identity
Immutable evidence
Manual payments test

ONE YEAR

Provider substitution
Carrier diversity
Enterprise reconciliation

Architecture acceptance requires service-level evidence

Each test must connect a dependency, control, result, limitation and owner.

- Recover with production identity unavailable.
- Investigate without the production monitoring plane.
- Validate the journal before service restoration.
- Demonstrate minimum viable payment capacity.

Design decisions should remove common modes before adding tools

Prioritize isolation, independent evidence and tested substitution.

01 Approve target recovery architecture

APPROVE

02 Assign technical owners and alternates

REQUIRE

03 Schedule evidence-based validation

REQUIRE