

Layout

Full-width desktop layout. Fixed top navigation bar. Single-column centered main content area with two sequential card containers (Identity Verification and Account Deletion). Modal overlay for final confirmation dialog. Fixed desktop footer at the bottom.

UI Structure

HEADER (Fixed Top): Web Navigation Bar — Desktop | [Logo] [Link: Home] [Link: About] [Link: Contact] [Button]

MAIN CONTENT AREA:

- Page Title: 'Delete Your Account' (H1, centered)
- Subtitle / Warning Banner: Prominent warning message explaining that account deletion is permanent and irreversible, and that all personal data will be removed from the system.
- Identity Verification Section (Card Container):
 - Section heading: 'Verify Your Identity'
 - [Form Field: Email Address] — pre-filled / read-only display of current user email
 - [Form Field: Password] — user must enter current password to confirm identity
 - Optional: [Form Field: 2FA / OTP Code] — if two-factor authentication is enabled
 - [Button: Verify & Continue] — primary action to proceed after identity check
- Account Deletion Section (Card Container, revealed after verification):
 - Section heading: 'Permanently Delete Account'
 - Bullet list of consequences: data removed, subscriptions cancelled, no recovery possible
 - [Checkbox: 'I understand that this action is permanent and cannot be undone']
 - [Button: Delete My Account] — destructive/danger-styled CTA (disabled until checkbox ticked)
 - [Link: Cancel — Return to Account Settings]
- Confirmation Dialog (Modal Overlay, triggered on 'Delete My Account' click):
 - Dialog Title: 'Are you sure?'
 - Dialog Body: Final confirmation message reiterating permanent data loss
 - [Button: Yes, Delete My Account] — final destructive confirmation
 - [Button: Cancel] — dismisses dialog, returns user to screen

FOOTER (Fixed Bottom): Web Footer — Desktop | [Link: Terms] [Link: Privacy] [Link: Contact] [Copyright & footer note] [Logo]

Layout Spec

- Viewport: Desktop ("1024px)
- Header: Fixed, full-width, height ~60px. Uses Web Navigation Bar — Desktop exactly as defined.
- Main Content Wrapper: max-width 720px, horizontally centered, top padding to clear fixed header (~80px), bottom padding above footer.
- Warning Banner: Full-width within content wrapper, visually distinct (e.g., alert/warning style), placed directly below page title.
- Card Containers: Rounded border containers, full width of content wrapper, vertically stacked with spacing between them.
- Identity Verification Card: Contains labeled form fields stacked vertically, with a primary [Verify & Continue] button aligned right or full-width at bottom.
- Account Deletion Card: Hidden/disabled until identity verified. Contains consequence list, checkbox, destructive [Delete My Account] button, and cancel link.
- Confirmation Dialog: Centered modal overlay, ~480px wide, with backdrop dimming the rest of the screen. Contains title, body text, and two action buttons side by side.
- Footer: Fixed or sticky at bottom, full-width. Uses Web Footer — Desktop exactly as defined.

Styling Spec

- Typography: H1 for page title, H2 for card section headings, body text for descriptions and consequence lists.
- Warning Banner: Visually distinct — use a warning/alert color token (e.g., amber/red background tint) with an icon prefix (e.g., warning icon).
- Destructive Button ([Delete My Account], [Yes, Delete My Account]): Danger/destructive styling (e.g., red fill) per design system button variants; disabled state until checkbox is checked.
- Primary Button ([Verify & Continue]): Standard primary button styling from design system.
- Checkbox: Standard form checkbox with clear label text.
- Cancel Link: Subdued/secondary text link styling.
- Modal Overlay: Semi-transparent backdrop; dialog card with elevated shadow.
- Form Fields: Standard input styling from design system; password field with show/hide toggle icon.
- Consistent iconography and spacing tokens as defined in the design system.

ASCII Wireframe

=== WEB (DESKTOP) — Account Deletion Screen ===

```
+-----+
| [Logo] [Link: Home] [Link: About] [Link: Contact] [Button ] | !• Fixed Nav Bar
+-----+
|
| Delete Your Account | !• H1 Page Title
|
| +-----+
| | WARNING: This action is permanent and cannot be | | !• Warning Banner
| | undone. All your personal data will be removed. | |
| | +-----+
| |
| | +-----+
| | VERIFY YOUR IDENTITY | | !• Card 1: Identity Verification
| | %%%%%%%%%%%%%%% | |
| | Email Address: | |
| | [user@example.com (read-only)] | |
| | | |
| | Password: | |
| | [Form Field: Enter your password] | |
| | | |
| | OTP / 2FA Code (if enabled): | |
| | [Form Field: Enter 6-digit code] | |
| | | |
| | [Button: Verify & Continue] | |
| | +-----+
| |
| | +-----+
| | PERMANENTLY DELETE ACCOUNT | | !• Card 2: Deletion (revealed post-verify)
| | %%%%%%%%%%%%%%% | |
| | Deleting your account will: | |
| | • Permanently remove all your personal data | |
| | • Cancel all active subscriptions | |
| | • Revoke access to all associated services | |
| | • This action CANNOT be reversed | |
| | | |
| | [ ] I understand this action is permanent and | |
| | cannot be undone. | |
| | | |
| | [Button: Delete My Account] (danger/red) | |
| | [Link: Cancel — Return to Account Settings] | |
| | +-----+
| |
| | ----- CONFIRMATION DIALOG (Modal) ----- |
| | +-----+
| | %%%%%%%%%%%%%%%%%%%%%%%%%%' |
```

Responsive Adaptation

- Navigation bar switches from Web Navigation Bar — Desktop to Web Navigation Bar — Mobile: [Logo] [Hamburger] only.
- Main content wrapper becomes full-width with horizontal padding (16px each side); max-width constraint removed.
- Warning Banner stacks to full width; font size reduced slightly.
- Card containers become full-width, edge-to-edge with padding inside.
- Form fields stack vertically, full-width inputs.
- Buttons become full-width on mobile web.
- Confirmation Dialog becomes a bottom sheet or full-screen modal on small viewports.
- Footer switches to Web Footer — Mobile: stacked links, logo on top, copyright at bottom.