XSafeClaw 安装指南

> **要求：** Python ≥ **3.11**，**macOS / Linux / Windows**。下文命令均在**终端**中执行（Windows：PowerShell / 命令提示符；macOS：终端；Linux：Terminal）。

一、环境准备

1. **确认 Python 版本**

   确认 Python 版本

   ```
   python3 --version
   ```

   需为 `3.11.x` 或更高。

2. **安装 Python**
   - **macOS：** `brew install python@3.11` 或官网安装包；终端执行 `python3 --version`。
   - **Linux：** `sudo apt install python3.11 python3.11-venv python3-pip`。
   - **Windows：** python.org/downloads 安装包，勾选 **Add python.exe to PATH**，装好后重开终端。

二、安装

xsafeclaw 安装

```
python3 -m pip install xsafeclaw
```

```
Requirement already satisfied: pyyaml>=5.1 in /opt/anaconda3/envs/xsafecl
aw/lib/python3.11/site-packages (from uvicorn[standard]>=0.27.0->xsafecla
w) (6.0.3)
Requirement already satisfied: uvloop>=0.15.1 in /opt/anaconda3/envs/xsaf
eclaw/lib/python3.11/site-packages (from uvicorn[standard]>=0.27.0->xsafe
claw) (0.22.1)
Requirement already satisfied: watchfiles>=0.20 in /opt/anaconda3/envs/xs
afeclaw/lib/python3.11/site-packages (from uvicorn[standard]>=0.27.0->xsa
feclaw) (1.1.1)
Downloading xsafeclaw-1.0.0-py3-none-any.whl (59.3 MB)
   ━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━━ 59.3/59.3 MB 16.3 MB/s  0:00:03
Installing collected packages: xsafeclaw
Successfully installed xsafeclaw-1.0.0
(xsafeclaw) repoan@RepoandeMacBook-Air xsafeclaw %
```

三、启动

启动 xsafeclaw

```
xsafeclaw start
```

```
(xsafeclaw) repoan@RepoandeMacBook-Air XSafeClaw % xsafeclaw start
🐾 XSafeClaw starting at http://127.0.0.1:6874
   Database: /Users/repoan/.xsafeclaw/data.db
INFO:     Started server process [22785]
INFO:     Waiting for application startup.
🚀 Starting XSafeClaw Application...
✅ Database initialized
🚀 Starting Message Sync Service...
📊 Performing initial scan...
Found 0 session files on disk
✅ Initial scan completed
📈 Initial scan: elapsed=0.01s, rss=89.1MB, pending_file_sync=0, pending_event_sync=0, track
ed_files=0, files=0
🔄 Syncing events for all sessions...
✅ Event sync completed: 0 events across 0 sessions
📁 Started watching: /Users/repoan/.openclaw/agents/main/sessions (poll=1s)
🔄 Post-watcher gap reconciliation...
Rechecking 0 session files after watcher startup
✅ Post-watcher gap reconciliation completed
📈 Post-watcher reconciliation: elapsed=0.00s, rss=89.1MB, pending_file_sync=0, pending_even
t_sync=0, tracked_files=0, files=0
✅ Message Sync Service started
✅ API server ready at http://0.0.0.0:6874
INFO:     Application startup complete.
INFO:     Uvicorn running on http://127.0.0.1:6874 (Press CTRL+C to quit)
 INFO:     127.0.0.1:55913 - "GET /api/guard/enabled HTTP/1.1" 200 OK
```

首次运行一般会**自动打开浏览器**引导页；未打开则访问 http://127.0.0.1:6874。

四、OpenClaw 安装引导

未检测到 OpenClaw 时，按页面引导操作，顺序一般为：

1. `http://127.0.0.1:6874/setup`：按提示安装 OpenClaw。

2. `http://127.0.0.1:6874/configure`：安全须知处勾选确认。

3. 引导模式选 **「快速开始」**（或手动模式）。

4. **模型：** 选择提供方（如 Qwen Cloud）→ 按「获取密钥」申请并粘贴 API Key。



5. **配置总览**核对无误后应用；初始化成功后，通过「进入智能体小镇」进入工作台。





6. 点击蓝色的 **“进入智能体小镇”** 按钮，此时你会看到一个充满设计感的像素风办公室，你的 Agent 们已经在这里待命了！

五、 进阶启动选项（开发者/服务器场景）

如果您在远程服务器（如 Linux）上使用，或者需要自定义端口，可以使用以下参数：

场景	命令	说明
自定义端口	xsafeclaw start --port 8080	当默认端口被占用时使用
局域网访问	xsafeclaw start --host 0.0.0.0	允许同局域网内其他设备访问
服务器模式	xsafeclaw start --no-browser	仅启动后台，不自动打开浏览器