

Dify Basic Features

Dify Basic Features

1. Course Content
2. Start the Dify Service
3. Basic Usage
 - 3.1 Switching the Dify Language
 - 3.1 Connecting Model Provider Services
 - 3.2 Switching the AI Application Model
4. Account Settings
5. Development Documentation

1. Course Content

- Understand and master the basic operations and functions of Dify.


2. Start the Dify Service

- Open the virtual machine and enter the command in the terminal:

```
sh ~/bringup_dify.sh
```

```
yahboom@yahboom:~$ sh ~/bringup_dify.sh
[+] up 13/13
✓ Container docker-sandbox-1      Running      0.0s
✓ Container docker-web-1          Running      0.0s
✓ Container docker-db_postgres-1  Healthy      22.5s
✓ Container docker-ssrf_proxy-1   Running      0.0s
✓ Container docker-redis-1        Running      0.0s
✓ Container docker-weaviate-1     Running      0.0s
✓ Container docker-worker-1       Running      0.0s
✓ Container docker-api_websocket-1 Running      0.0s
✓ Container docker-plugin_daemon-1 Running      0.0s
✓ Container docker-worker_beat-1  Running      0.0s
✓ Container docker-api-1          Running      0.0s
✓ Container docker-nginx-1        Running      0.0s
✓ Container docker-init_permissions-1 Exited      28.4s
yahboom@yahboom:~$
```

- Check the IP address of the virtual machine by clicking "Robot Information" on the left side of the desktop.



- Enter the vehicle IP address directly in the browser address bar to access the Dify management page. If the device is logging in for the first time, you need to use the account and password. You can select the language in the upper-left corner.

i Note

- Account: `yahboom@163.com`
- Password: `yahboom123`
- All account passwords, agent applications, and RAG data are stored locally.
- The Dify main interface is shown below:





3. Basic Usage

💡 Tip

- If you need to use the cloud AI models of model providers, please make sure the virtual machine is connected to the internet.

3.1 Switching the Dify Language


- Generally, the Dify page follows the browser language after opening. If you need to switch manually, you can switch the language in the Settings.




3.1 Connecting Model Provider Services

- Dify has built-in model interface plugins for different model providers. These plugins are maintained and upgraded by their respective model providers. We can install the plugins of the corresponding model providers to quickly connect to cloud models from different vendors.
- Click "Plugins" in the upper-left of the homepage —> "Explore Marketplace" —> "Model" to enter the

model interface plugin page.




- Here, the installation and configuration of the Qwen plugin is used as an example. Other plugins use the same method; just click "Install".



- Then, in the "Model Provider" section of the "Settings" page, fill in the API-KEY applied for from the corresponding platform. If the API-KEY is valid, the "APIKEY" of the corresponding plugin will show a green light.


💡 Tip

- For more detailed `API-KEY` configuration steps and methods to test the `API-KEY`, refer to [6](#).
Configure `API-KEY` in the previous chapter.




3.2 Switching the AI Application Model


- For already-developed AI agent applications, you can quickly switch between different models to test the effects of different models. Here, we use the core agent microros-v2-zh of MICROROS-V2 as an example. Open the agent application on the homepage.



- There are four core AI components: task routing, decision-layer AI, execution-layer AI, and the box-selection layer.



- Here, switching the decision-layer AI is used as an example. Open the "Decision-Layer AI" card and use the dropdown in the model selection bar to switch to models from different providers. Here, qwen3.6-plus is selected.




- We can also fine-tune the model's reply effect through parameters. Each parameter can be viewed for its detailed effect by hovering the mouse over it.
- Taking the temperature parameter as an example:


Used to control the degree of randomness and diversity. The temperature value controls how much the probability distribution of each candidate word is smoothed when generating text. A higher temperature value lowers the peaks of the probability distribution, causing more low-probability words to be selected and making the generated results more diverse; a lower temperature value strengthens the peaks of the probability distribution, making high-probability words more likely to be selected and the generated results more deterministic.

💡 Tip

- Beginners can generally use the default parameters; no adjustment is needed.




- Note that after modifying an AI application, you need to click "Publish" — "Publish Update" to save the changes.



Warning

Please note

- For the execution-layer and box-selection-layer models, because they need to process images, only multimodal models can be used (vision models have a special symbol marker as shown in the figure below).
- Task routing and decision-layer models have no restrictions.
- Task routing can use small-parameter models to improve response speed.



Box-selection layer model:

The image shows a configuration panel for a 'Bounding-Box Layer AI' model. On the left, a workflow diagram includes nodes for 'ASSIGN BOUNDING BOX', 'BOUNDING-BOX LAYER AI', and 'EXECUTE'. A red arrow points from the 'BOUNDING-BOX LAYER AI' node to the configuration panel on the right. The panel has tabs for 'SETTINGS' and 'LAST RUN'. Under 'SETTINGS', the 'MODEL' dropdown is set to 'kimi-k2.5'. Below this is a 'CONTEXT' section with a 'Set variable' button. The 'SYSTEM' section contains a detailed prompt for the robot's role and output format, including a JSON schema and field rules.

Bounding-Box Layer AI

Add description...

SETTINGS **LAST RUN**

MODEL *

kimi-k2.5 CHAT

CONTEXT ⓘ

(x) Set variable

SYSTEM ⓘ 1958 Jinja (x)

You are the target bounding-box layer of the MicroROS-V2 robot. You have exactly one responsibility: return bbox coordinates suitable for tracking based on the image and target description.

Do not control the robot, plan steps, call action functions, or explain the workflow.

Output format


Output only a strict JSON object:

```
```json
{"found":true,"target":"target name","bbox":
[x1,y1,x2,y2],"confidence":0.0,"reason":"brief
explanation"}
```
```

Field rules:

1. `found`: whether the target can be uniquely

If the vision variable is not selected, scroll down to select it.




4. Account Settings

📘 Note

The Dify account is stored locally and has no privacy risks. MICROROS-V2 comes with a preset administrator account at the factory. Only refer to this section of the tutorial if you need to modify the account information.

- Click the avatar in the upper-right corner —> Account.



- The account information is as follows. You can modify the information as needed.

My Account



yahboom
yahboom@163.com

Name

yahboom

Edit

Email

yahboom@163.com

Change

Password

You can set a permanent password if you don't want to use temporary login codes

Reset password

Account's data

The user data of your account.

Show 5 apps

>

- If you need to log out, click the avatar again to log out.


yahboom
yahboom@163.com



⌵ Log out

5. Development Documentation

- For users with in-depth development needs later, you can view more detailed development documentation by clicking the avatar in the upper-right corner —> "View Help Documentation".



- Then the Dify online development documentation page will open. You can select different documentation content to view from the dropdown list on the left.

