

1. Change the hostnames
##Use the 'hostname'
2. Configure an unencrypted password
3. Exit back to user EXEC
4. View the password in
5. Ensure that the current
6. View the password in t
7. Configure a more secu
8. Exit back to user EXEC
Which password do yo
9. View the passwords in
What encryption type
What encryption type
10. Save the running con


```
R1>enable
Password:
R1#conf t
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#enable secret ?
  0      Specifies an UNENCRYPTED password will follow
  5      Specifies an ENCRYPTED secret will follow
  LINE   The UNENCRYPTED (cleartext) 'enable' secret
  level  Set exec level password
R1(config)#enable secret Yahyak
enable
Password:
R1#show r
R1#show running-config
Building configuration...

Current configuration : 771 bytes
!
version 15.1
no service timestamps log datetime msec
no service timestamps debug datetime msec
service password-encryption
!
hostname R1
!
enable secret 5 $1$mERr$/Y6k9CuogW4tKGWiWpTcO.
enable password 7 08384D4610180E
```

Copy

Paste

File Edit Options View Tools Extensions Window Help




```
R1
Physical    Config    CLI    Attributes

*LINEPROTO-5-UPDOWN: line protocol on Interface GigabitEthernet0/0, changed state to up

Router#enable
Router#hostname

% Unknown command or computer name, or unable to find computer address

Router#enable
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname
% Incomplete command,
Router(config)#hostname?
hostname
Router(config)#hostname?
hostname
Router(config)#hostname ?
WORD This system's network name
Router(config)#hostname R1
R1(config)#exit
R1#
%SYS-5-CONFIG_1: Configured from console by console
exit
```



```
R1#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
R1(config)#enable password?
password
R1(config)#enable password ?
 7          Specifies a HIDDEN password will follow
LINE       The UNENCRYPTED (cleartext) 'enable' password
level      Set exec level password
R1(config)#enable password yahyak
R1(config)#exit
R1#
%SYS-5-CONFIG_I: Configured from console by console

R1#exit
```

```
R1>enable
Password:
R1#sh run
Building configuration...

Current configuration : 717 bytes
!
version 15.1
no service timestamps log datetime msec
no service timestamps debug datetime msec
no service password-encryption
!
hostname R1
!
!
!
enable password yahyak
!
!
!
!
!
!
ip cef
no ipv6 cef

R1#
```