

CS202

HW No. 4

Section No. 02

Yassin Younis

22101310

Inserting 7 into AVL tree: 7 Inserting 91 into AVL tree: 7 91 Inserting 3 into AVL tree: 7 / \ 3 91 Inserting 24 into AVL tree: 7 3 91 24 Inserting 12 into AVL tree: 7 / \ 3 24 /\ 12 91 Inserting 33 into AVL tree: 24 7 91 /\ 3 12 33 Inserting 45 into AVL tree: 24 45 /\ / \ 3 12 33 91 Inserting 61 into AVL tree: 24 7 45 /\ / \ 3 12 33 91 61 Inserting 57 into AVL tree: 24 7 45 /\ / \ 3 12 33 61

> /\ 57 91

Deleting 3 from AVL tree:

Deleting 61 from AVL tree:

Deleting 45 from AVL tree:

7

Inserting 7 into 2-3 tree:

Inserting 91 into 2-3 tree: 7|91

Inserting 3 into 2-3 tree:

7 /\ 3 91

Inserting 24 into 2-3 tree:

7 / \ 3 24|91

Inserting 12 into 2-3 tree: 7|24

/ \mid \ 3 12 91 Inserting 33 into 2-3 tree:

7|24 / | \ 3 12 33|91 Inserting 45 into 2-3 tree: 24 / \ 7 45 / \ / \ 3 12 33 91 Inserting 61 into 2-3 tree: 24 / \ 7 45 / \ / 3 12 33 61|91 Inserting 57 into 2-3 tree: 24 \ 7 45|61 / \ / | \ 3 12 33 57 91 Deleting 3 from 2-3 tree: 45 / \ 24 61 / \ 7|12 33 57 91 Deleting 61 from 2-3 tree: 24|45 7|12 33 57|91 Deleting 45 from 2-3 tree: 24|57 \ 7|12 33 Inserting 7 into 2-3-4 tree: Inserting 91 into 2-3-4 tree: 7|91 Inserting 3 into 2-3-4 tree: 3|7|91 Inserting 24 into 2-3-4 tree: 7 / \ 3 24|91 Inserting 12 into 2-3-4 tree: 7

3 12|24|91

Inserting 33 into 2-3-4 tree:

7|24 / | \ 3 12 33|91

Inserting 45 into 2-3-4 tree:

7|24 / | \ 3 12 33|45|91

Inserting 61 into 2-3-4 tree:

7|24|45 / | | \ 3 12 33 61|91

Inserting 57 into 2-3-4 tree:

7|24|45 / | | \ 3 12 33 57|61|91

Deleting 3 from 2-3-4 tree:

24|45 / | \ 7|12 33 57|61|91

Deleting 61 from 2-3-4 tree:

24|45 / | \ 7|12 33 57|91

Deleting 45 from 2-3-4 tree:

24|57 / | \ 7|12 33 91