

## Joining a Windows Machine to the Domain

Group: 3

Logan Haberman, Braden Yokopenic, Joseph Turkovich

- 1. We first need to change our VM's network. To do this:
  - a. Click actions
  - b. Find and click **Edit Settings**
  - c. Find **Network Adapter 1** and change it to **GroupX** with X being your group number






2. Next log into your VM. And navigate to the bottom right corner of your screen and right-click the Wi-Fi icon and click **Network and Internet Settings.** 




3. When in the network settings scroll down to find **Advanced network** settings




- 4. Once in the Advanced network settings find **Ethernet** and click the down arrow on the left side of the box.
- 5. From the drop down menu, you should see More adapter options. Click Edit



6. You should now see the **Ethernet0 Properties** pop-up. In the box find **Internet Protocol Version 4(TCP/IPv4)**, select it and click the **Properties** box.




7. You will then see the **Properties** pop-up. In this pop-up click the bubble that says **Use the following IP address.** 




8. Enter the **IP address** for your Windows machine so it is on the same network as your server. **Ex: 172.16.3.25** 

- 9. Enter the Subnet mask as 255.255.255.0
- 10. Enter the **Default gateway** so it is the same as your server's. **EX: 172.16.3.1**
- 11. Select the bubble for **Use the following DNS server addresses:**
- 12. Enter the **IP** of your server. **Ex: 172.16.5.10**
- 13. Select OK
- 14. Next, go back to the windows settings and fins the Accounts tab.
- 15. Once clicked on Accounts, find Access work or school.




16. Once in the Access work or school tab, find the **Add a work or school account** and click **Connect** 

17. Once you should see or school we will not Instead, go pop-up and device to a Directory




click connect, You the Set up a work account pop-up, be filling that out. to the bottom of the click Join this local Active domain.


- 18. This will open the **Join a domain** pop-up where you can enter the domain you want to join. **Ex: YourDomain.local.**
- 19. Click Next.



20. You will then be prompted to enter the User name and password for the domain you are trying to join. For our case, we will enter the user name: **Administrator** and the Password: **Rajah424!** 



21. It will then ask you to add an account. Keep both the default it sets and click Next.



22. It will then ask you to Reboot.

23. After rebooting you should be able to log into the VM as a member of the domain.

