```
entry
```

```
L0
LINENUMBER 32 L0
LDC "ee8d6823-ab1f-4c93-9f85-1513ed26ece0"
INVOKESTATIC edu/cmu/cs/mvelezce/tool/analysis/region/RegionsCounter.enter (Ljava/lang/String;)V
ICONST_0
ISTORE 3
L1
LINENUMBER 34 L1
ILOAD 0
IFEQ L2
```

```
L3
LINENUMBER 35 L3
LDC 1000
INVOKESTATIC java/lang/Thread.sleep (J)V
L4
LINENUMBER 36 L4
ILOAD 2
INVOKESTATIC edu/cmu/cs/mvelezce/Example.moo (Z)V
L5
LINENUMBER 37 L5
ICONST_1
ISTORE 3
```

```
L2
LINENUMBER 40 L2
FRAME APPEND [I]
LDC "ee8d6823-ab1f-4c93-9f85-1513ed26ece0"
INVOKESTATIC edu/cmu/cs/mvelezce/tool/analysis/region/RegionsCounter.exit (Ljava/lang/String;)V
LDC "c85f911f-d0ae-4bca-8dfe-e49d1e5a7536"
INVOKESTATIC edu/cmu/cs/mvelezce/tool/analysis/region/RegionsCounter.enter (Ljava/lang/String;)V
ILOAD 1
IFEQ L6
```

```
ILOAD 3
LDC "41dc8918-60e4-4db7-aadc-cb819df16e44"
INVOKESTATIC edu/cmu/cs/mvelezce/tool/analysis/region/RegionsCounter.enter (Ljava/lang/String;)V
IFEQ L6
```

```
L7
LINENUMBER 41 L7
LDC 2000
INVOKESTATIC java/lang/Thread.sleep (J)V
```

```
L6
LINENUMBER 43 L6
FRAME SAME
LDC "41dc8918-60e4-4db7-aadc-cb819df16e44"
INVOKESTATIC edu/cmu/cs/mvelezce/tool/analysis/region/RegionsCounter.exit (Ljava/lang/String;)V
LDC "c85f911f-d0ae-4bca-8dfe-e49d1e5a7536"
INVOKESTATIC edu/cmu/cs/mvelezce/tool/analysis/region/RegionsCounter.exit (Ljava/lang/String;)V
RETURN
```

```
exit
```