

konfiguracja mikrotika

admin@192.168.1.10 (MikroTik) - WinBox v6.45.9 on hAP lite (omips)

Session Settings Dashboard

Safe Mode Session: 192.168.1.10

Quick Set CAPsMAN Interfaces Wireless Bridge PPP Switch Mesh IP MPLS Routing System Queues Files Log RADIUS Tools New Terminal Make Supout of New WinBox Exit Windows

DHCP Server

Address	Gateway	DNS Servers	Domain	WINS Servers	Next Server
192.168.1.0/24	192.168.1.10	8.8.8.8			
192.168.10.0/24	192.168.10.1	8.8.8.8			
192.168.20.0/24	192.168.20.1	8.8.8.8			
192.168.88.0/24	192.168.88.1				

4 items (1 selected)

Interface List

Interface	Interface List	Ethernet	EoIP Tunnel	IP Tunnel	GRE Tunnel	VLAN	VRRP	Bonding	LTE
R	VLAN10	VLAN							
R	VLAN20	VLAN							

2 items out of 9 (1 selected)

admin@192.168.1.10 (MikroTik) - WinBox v6.45.9 on hAP lite (omips)

Session Settings Dashboard

Safe Mode Session: 192.168.1.10

Quick Set CAPsMAN Interfaces Wireless Bridge PPP Switch Mesh IP MPLS Routing System Queues Files Log RADIUS Tools New Terminal Make Supout of New WinBox Exit Windows

IP Pool

Name	Addresses	Next Pool
ip_pool1	192.168.10.2-192.168.10.254	none
ip_pool2	192.168.20.2-192.168.20.254	none


3 items

Interface List



Interface	Interface List	Ethernet	EoIP Tunnel	IP Tunnel	GRE Tunnel	VLAN	VRRP	Bonding	LTE
R	VLAN10	VLAN							
R	VLAN20	VLAN							

2 items out of 9 (1 selected)

vlny na switchu p2



vlany na switchu p1



adresy na serwerze

```
Administrator: Wiersz polecenia
Default Gateway . . . . . :
Ethernet adapter LAN1:
    Connection-specific DNS Suffix  . :
    Link-local IPv6 Address . . . . . : fe80::b1d8:d67c:a7bd:4cba%27
    Default Gateway . . . . . :
C:\Users\Administrator>ipconfig /renew
Windows IP Configuration

Ethernet adapter LAN2:
    Connection-specific DNS Suffix  . :
    Link-local IPv6 Address . . . . . : fe80::58ea:95b5:725:48c3%13
    IPv4 Address. . . . . : 192.168.20.251
    Subnet Mask . . . . . : 255.255.255.0
    Default Gateway . . . . . : 192.168.20.1

Ethernet adapter LAN1:
    Connection-specific DNS Suffix  . :
    Link-local IPv6 Address . . . . . : fe80::b1d8:d67c:a7bd:4cba%27
    IPv4 Address. . . . . : 192.168.10.5
    Subnet Mask . . . . . : 255.255.255.0
    Default Gateway . . . . . : 192.168.10.1
C:\Users\Administrator>
```

adresy na stacji

```
C:\WINDOWS\system32\cmd.exe
Default Gateway . . . . . :
Ethernet adapter LAN1:
    Connection-specific DNS Suffix  . :
    Link-local IPv6 Address . . . . . : fe80::1327:c8d3:20fa:5128%15
    Default Gateway . . . . . :
C:\Users\User>ipconfig /renew
Windows IP Configuration

Ethernet adapter LAN2:
    Connection-specific DNS Suffix  . :
    Link-local IPv6 Address . . . . . : fe80::c2a6:bffe:bfc1:5b6d%18
    IPv4 Address. . . . . : 192.168.10.4
    Subnet Mask . . . . . : 255.255.255.0
    Default Gateway . . . . . : 192.168.10.1

Ethernet adapter LAN1:
    Connection-specific DNS Suffix  . :
    Link-local IPv6 Address . . . . . : fe80::1327:c8d3:20fa:5128%15
    IPv4 Address. . . . . : 192.168.20.252
    Subnet Mask . . . . . : 255.255.255.0
    Default Gateway . . . . . : 192.168.20.1
C:\Users\User>
```