

MOTADATA-8503 — Manual Test Cases

Unified Create Policy UI (Metric/APM/RUM/NetRoute). Jira: <http://172.16.10.6:8080/browse/MOTADATA-8503>

TC-8503-01 — Metric Threshold policy via unified Set Conditions

Module: Metric **Risk:** smoke **Traces to:** A1, A2, B1, B2, B3, B4, D4 **Jira:** TC-8503-01

Preconditions: logged in; a Linux monitor exists (env Sybase_linux_ip)

Steps:

1. navigate: Settings > Policy Settings
2. click: Create Policy (lands on Metric module)
3. select Set Conditions card: Threshold Alert
4. fill: Policy Name = 8503-Metric-Threshold
5. add tags: motadata:8.61, Automation@zen
6. select: Counter = system.cpu.percent
7. select: Source Filter = Monitor; pick monitor row {{ip}} (Linux)
8. fill severity: critical=85, major=75, warning=60
9. verify operator dropdown (Equals/Greater/Less) selectable & persists
10. click: Create Policy

Expected: success toast appears; redirect to policy list; 8503-Metric-Threshold visible

Edge cases: empty Policy Name + click Create -> validate-on-submit, required field highlighted, no create; empty Counter -> field highlighted red, save blocked

TC-8503-02 — APM Baseline policy via unified Set Conditions

Module: APM **Risk:** high **Traces to:** A1, A2, B2, B3, B5, D1 **Jira:** TC-8503-02

Preconditions: logged in; APM service source Checkout Service exists

Steps:

1. navigate: Settings > Policy Settings > Create Policy
2. select module: APM (in-panel)
3. set APM Policy Type = Trace Metrics (filters counters)
4. fill: Policy Name = 8503-APM-Baseline
5. select Set Conditions card: Baseline Alert
6. select: Counter = Avg Response Time
7. select: Source Filter = Service; Source = Checkout Service
8. configure baseline params + Abnormality Occurrence / Auto Clear
9. click: Create Policy

Expected: success toast + policy visible as Baseline type

Edge cases: switch Policy Type to Trace Analytics -> counter list changes (D1); Baseline tab present for APM (new vs old build)

TC-8503-03 — RUM Anomaly policy via unified Set Conditions

Module: Real User Monitoring **Risk:** high **Traces to:** A1, A2, A3, B2, B5, D2 **Jira:** TC-8503-03

Preconditions: logged in; RUM application source Customer Portal exists

Steps:

1. navigate: Settings > Policy Settings > Create Policy

2. select module: Real User Monitoring (in-panel)
3. fill: Policy Name = 8503-RUM-Anomaly
4. select Set Conditions card: Anomaly
5. select: Counter = Page Load Time
6. select: Source Filter = Application; Source = Customer Portal
7. configure occurrence threshold
8. click: Create Policy

Expected: policy created without leaving Create Policy flow (A3); only RUM-eligible counters shown (D2)

Edge cases: Anomaly is a card here, not a separate standalone flow (A3)

Impact / Affected (known):

- Standalone Anomaly/Forecast creation flows are removed — any saved links/bookmarks/docs pointing to old flows are affected.

TC-8503-04 — NetRoute Forecast policy via unified Set Conditions

Module: NetRoute **Risk:** high **Traces to:** A1, A2, A3, B2, D3 **Jira:** TC-8503-04

Preconditions: logged in; NetRoute interface source WAN Interface exists

Steps:

1. navigate: Settings > Policy Settings > Create Policy
2. select module: NetRoute (in-panel hrefless link, not global sidebar)
3. fill: Policy Name = 8503-NetRoute-Forecast
4. select Set Conditions card: Forecast
5. select: Counter = Link Utilization
6. select: Source Filter = Interface; Source = WAN Interface
7. configure forecast horizon / threshold
8. click: Create Policy

Expected: forecast policy created in unified flow; only NetRoute-eligible counters/source filters shown (D3)

Edge cases: clicking NetRoute in-panel must NOT navigate to /netroute/ module

Impact / Affected (known):

- Standalone Anomaly/Forecast creation flows are removed — any saved links/bookmarks/docs pointing to old flows are affected.

TC-8503-05 — Set Conditions exposes four cards in correct order

Module: Metric **Risk:** smoke **Traces to:** A2 **Jira:** TC-8503-05

Preconditions: logged in

Steps:

1. navigate: Settings > Policy Settings > Create Policy (Metric)
2. observe Set Conditions section

Expected: exactly four cards: Threshold Alert | Baseline Alert | Anomaly | Forecast, in order

TC-8503-06 — Edit existing Threshold policy renders in unified screen and persists

Module: APM/RUM/NetRoute (one with an existing Threshold policy) **Risk:** high **Traces to:** A1, F1, B4 **Jira:** TC-8503-06

Preconditions: an existing Threshold policy exists

Steps:

1. navigate: Settings > Policy Settings

2. open an existing Threshold policy (edit)
3. verify it renders in unified layout, Threshold card selected
4. update a severity threshold value
5. click: Save / Update Policy
6. reopen the same policy

Expected: updated value persisted (F1)

Impact / Affected (known):

- Existing Threshold policies (Metric/APM/RUM/NetRoute) must keep working unchanged — regression risk from unified UI.

TC-8503-07 — Backward compatibility — existing Anomaly/Forecast policies still function

Module: any **Risk:** edge **Traces to:** F2, A3 **Jira:** TC-8503-07

Preconditions: a pre-existing Anomaly or Forecast policy exists

Steps:

1. navigate: Settings > Policy Settings
2. locate an existing Anomaly/Forecast policy
3. open it

Expected: opens on the matching card in the unified screen; no error; values intact (F2)

Impact / Affected (known):

- Existing Anomaly/Forecast policies must still open & function in the unified screen.
- Standalone Anomaly/Forecast creation flows are removed — any saved links/bookmarks/docs pointing to old flows are affected.

TC-8503-08 — Validation — Policy Name and Counter gating (validate-on-submit)

Module: Metric **Risk:** smoke **Traces to:** B1, B2 **Jira:** TC-8503-08

Preconditions: logged in

Steps:

1. navigate: Settings > Policy Settings > Create Policy (Metric)
2. with empty form, click Create Policy
3. observe required fields highlighted; no policy created
4. fill Policy Name only; leave Counter empty; click Create Policy

Expected: Create Policy stays enabled but submit is blocked while required fields empty; Counter required on all four cards (B2)