CS 2200 Homework 4

Fall 2018

Rules:

- Please print a copy of the assignment and hand write your answers. No electronic submissions are allowed. Please print as one double-sided page. Do NOT staple multiple sheets together.
 There will be a 40 point penalty if you do not.
- This is an individual assignment. You may discuss concepts but not the answers.
- Due Date: 26 September 2018 6:00 PM. Bring your BuzzCard. Show up on time.

Name:	·	GT Username:	Section:
1.	What is the IVT, what does it store, and where	is it located?	
2.	Why is it necessary to disable interrupts in the	INT macrostate when you enter the	e interrupt handler?
3.	Consider the table below. You find some way to increase the cycle time. What is the maximum change beneficial?		

Instruction type	Cycles	Frequency in program
А	2	30%
В	6	50%
С	5	20%

4. Complete the following interrupt handler by filling in the missing assembly code. Assume the processor has already placed PC in \$k0, disabled interrupts, and set the PC of the first instruction in int. handler.

We've given you the main logic of the handler, which simply increments a counter in memory. Your completed handler must allow nested interrupts, i.e., another interrupt should be permitted to come in while the handler is running. Do not leave interrupts disabled longer than absolutely necessary. Only save the minimum of registers absolutely necessary.

Here are the new instructions we added to LC-2200 for interrupt handling:

- EI enable the ability for interrupts to occur
- **DI** disable the ability for interrupts to occur
- **RETI** set PC = \$k0 and enable interrupts

int_ha	ndler:	
addi	\$sp, \$sp,	
SW	, 0x0(\$sp)	
addi	,, -2	
SW	, 0x1(\$sp)	
SW	, 0x0(\$sp)	
! main	interrupt handler logic b	pegins
lea	\$t0, counter	! load address of counter into \$s0
lw	\$t1, 0x0(\$t0)	! load value of counter into \$s1
addi	\$t1, \$t1, 1	! add 1 to counter value
SW	\$t1, 0(\$t0)	! store new counter value in memory
! main	interrupt handler logic e	ends
	\$t0, 0x1(\$sp)	
	\$t1, 0x0(\$sp)	
addi	,, 2	
	,(\$sp)	
addi	\$sp,,	
counte	r: .fill 0x0	! external counter