

High Performance Computing

高性能計算論

Volume 1

Cyberscience Center, Tohoku Univ

Hiroyuki Takizawa takizawa@tohoku.ac.jp



Instructor

■ Hiroyuki TAKIZAWA (滝沢寛之)

- Processor at Cyberscience Center
- Research Interests
 - High-performance computing software and systems
 - Computer architectures
 - Parallel and distributed computing systems and apps

E-mail: takizawa@tohoku.ac.jp

http://www.sc.cc.tohoku.ac.jp/~tacky

HPC Lab (Takizawa lab)

System Operation



Performance-Aware Programming

Different kinds of processors available on a system













Application Optimization







Supercomputer as an Infrastructure working with sensors and IoT devices

Exploring Next-Gen Supercomputing Technologies



Class Schedule (tentative!)

1-Oct	Introduction to HPC (1)
1-0ct	Introduction to HPC (2)
8-Oct	Parallel Architectures
8-Oct	How to use Supercomputer AOBA
15-Oct	Parallel Algorithm Design (1)
15-Oct	Parallel Algorithm Design (2)
5-Nov	MPI Programming (1)
5-Nov	MPI Programming (2)
12-Nov	OpenMP Programming (1)
12-Nov	OpenMP Programming (2)
26-Nov	Hybrid Programming
26-Nov	Performance Modeling and Analysis




Introduction

- **■** High Performance Computing (HPC)
 - An HPC system is often called a Supercomputer
 - What parallel computing is and why it's growing in importance.
 - Where parallelism exists in modern hardware.
 - Why the amount of parallelism in application software is important.
 - How to exploit parallelism.

What is a supercomputer?




Modern Scientific Method




Target Applications

Next-Generation SuperSonic Transport







Perpendicular Magnetic Recording Medium Design




Nano Material Design




Earthquake Analysis




Antenna Analysis





142 143 144 145

Combustion Flow Simulation





Ozone-hole Analysis



MRJ

Boundary Value Problem







Difference Method (1/2)

■ Heat conduction

Temparature at location x and time t

$$\frac{\partial u(x,t)}{\partial t} = \frac{\partial^2 u(x,t)}{\partial x^2}$$

$$\frac{\partial u(x)}{\partial x} \approx \lim_{h \to 0} \frac{u(x+h) - u(x)}{h}$$

$$\frac{\partial^2 u(x)}{\partial x^2} \approx \lim_{h \to 0} \frac{u(x+h) - u(x)}{h^2} - \frac{u(x) - u(x-h)}{h^2}$$

$$= \lim_{h\to 0} \frac{u(x+h)-2u(x)+u(x-h)}{h^2}$$




Difference Method (2/2)

■ Heat conduction

$$\frac{\partial u(x,t)}{\partial t} = \frac{\partial^2 u(x,t)}{\partial x^2}$$

$$\frac{u(t+\Delta t)-u(t)}{\Delta t} = \frac{u(x+\Delta x)-2u(x)+u(x-\Delta x)}{\Delta x^2}$$

Temperature at time step $t+\Delta t$ can be calculated by using the current temperatures of each location and its neighbors.



The simulation becomes more precise for smaller Δt and Δx , but needs more calculations (more locations and time steps) when the rod length and period are fixed. \rightarrow More computing power is needed for numerical simulation.



Target Applications (Cont'd)

■ Al and ML will be the predominant users?





Figure 1 Language modeling performance improves smoothly as we increase the model size, datasetset size, and amount of compute² used for training. For optimal performance all three factors must be scaled up in tandem. Empirical performance has a power-law relationship with each individual factor when not bottlenecked by the other two.

Floating-Point Notation of Numbers

■ Floating-point notation

- A number is represented by a mantissa (significand) and an exponent, similar to scientific notation
- Representable range extended
- Complicated processing needed for arithmetic operations



FLOPS! Flops! flop/s!

- Strong demand for high performance on floating-point operations.
 - Numerical simulation of physical phenomena requires a huge number of floating-point operations.
 - = a supercomputer must run it in practical time
- A supercomputer is super in terms of FP operation performance
- **■** Floating-point operation rate (FLOPS rate)
 - The performance of a supercomputer is discussed based on how many floating-point operations the supercomputer can execute per unit time.

The number of **fl**oating-point **op**erations per **s**ec = FLOPS, Flops, flop/s



Prefixes

Chinese Characters	S	SI Prefixes	
(KANJI)		(Intl. Syst. of Unit)	
■ 万 (man)	: 104	■ K (kilo)	: 10 ³
■ 億 (oku)	: 108	■ M (mega)	: 10 ⁶
■兆 (chou)	: 10 ¹²	■ G (giga)	: 10 ⁹
■ 京 (kei)	: 10 ¹⁶	■ T (tera)	: 1012
■ 垓 (gai)	: 10 ²⁰	■ P (peta)	: 10 ¹⁵
■	: 10 ²⁴	► E (exa)	: 10 ¹⁸
■ 穣 (jou)	: 10 ²⁸	Z (zetta)	: 10 ²¹
• • •		■\Y (yotta)	: 10 ²⁴
■ 無量大数	: 10 ⁶⁸	K Computer = 10 Pflop/s =	10 ¹⁶

https://www.top500.org/

Rank	System	Cores	Rmax (PFlop/s)	Rpeak (PFlop/s)	Power (kW)
Num	· •	30103	•	(, ι τορ/ σ/	
1	Frontier - HPE Cray EX235a, AMD Optimized 3rd Generation EPYC 64C 2GHz, AMD Instinct MI250X, Slingshot-11, HPE DOE/SC/Oak Ridge National Laboratory United States	8,699,904	1,206.00	1,714.81	22,786
2	Aurora - HPE Cray EX - Intel Exascale Compute Blade, Xeon CPU Max 9470 52C 2.4GHz, Intel Data Center GPU Max, Slingshot-11, Intel DOE/SC/Argonne National Laboratory United States	9,264,128	1,012.00	1,980.01	38,698
3	Eagle - Microsoft NDv5, Xeon Platinum 8480C 48C 2GHz, NVIDIA H100, NVIDIA Infiniband NDR, Microsoft Azure Microsoft Azure United States	2,073,600	561.20	846.84	
4	Supercomputer Fugaku - Supercomputer Fugaku, A64FX 48C 2.2GHz, Tofu interconnect D, Fujitsu RIKEN Center for Computational Science Japan	7,630,848	442.01	537.21	29,899
5	LUMI - HPE Cray EX235a, AMD Optimized 3rd Generation EPYC 64C 2GHz, AMD Instinct MI250X, Slingshot-11, HPE EuroHPC/CSC Finland	2,752,704	379.70	531.51	7,107
6	Alps - HPE Cray EX254n, NVIDIA Grace 72C 3.1GHz, NVIDIA GH200 Superchip, Slingshot-11, HPE Swiss National Supercomputing Centre (CSCS) Switzerland	1,305,600	270.00	353.75	5,194
7	Leonardo - BullSequana XH2000, Xeon Platinum 8358	1,824,768	241.20	306.31	7,494



Italy

32C 2.6GHz, NVIDIA A100 SXM4 64 GB, Quad-rail NVIDIA

What is Parallel Computing?



What is Parallel Computing?


- **Parallel Computing**
 - = execution of many operations at a time.
- **■** Parallel Computing is the practice of ...
 - Identifying and exposing parallelism in algorithms
 - Expressing the parallelism in the software implementation
 - Understanding the costs, benefits, and limitations of the chosen implementation
- **■** Parallel computing is about "performance"
 - There could be various definitions of performance.
 - Ex) Speedup, Problem Size, Energy Efficiency



Why Parallel Computing?

■ A computer no longer becomes faster but more parallel

50 Years of Microprocessor Trend Data



Original data up to the year 2010 collected and plotted by M. Horowitz, F. Labonte, O. Shacham, K. Olukotun, L. Hammond, and C. Batten New plot and data collected for 2010-2021 by K. Rupp

Horowitz et al. and Rupp, https://github.com/karlrupp/microprocessor-trend-data

Clock Frequency and Power

■ Power consumption quickly increases with the clock frequency.

$$P_d = \alpha \times f \times V_{dd}^2$$

 P_d : dynamic power consumption

f: clock frequency

 V_{dd} : power-supply voltage

Note f is correlated with V_{dd} .

 \rightarrow P_d increases at the rate of $O(f^3)$ if f is proportional to V_{dd} .

Power Saving by Parallel Comp.

- Let's calculate the power consumption of each system configuration.
 - System 1: Processor A x 1 $f = 2GHz, V_{dd} = 1.5V$ $P_d = \alpha \times 2000 \times 1.5 \times 1.5 = 4500\alpha$
 - System 2: Processor B x 4 $f = 500MHz, V_{dd} = 0.8V$ $P_d = \alpha \times 500 \times 0.8 \times 0.8 \times 4 = 1280\alpha$

If 4 processors of System 2 work perfectly in parallel, System 2 is expected to achieve the same performance as System 1. The power consumption of System 2 is only about 28% of that of System 1.


→ Parallel computing is power-effective.




Where Parallelism Exists




System Overview



System Overview




System Overview



Software Overview

When a program is launched, several kinds of resources such as CPU time and memory are allocated for the execution. A unit of allocated resource is called a **process**. An **application** (user program) is executed by multiple processes.



The OS on each node decides the core(s) to execute the process. A process can be executed by multiple cores. The execution sequence on each core is called a **thread**.



Benefit of Parallel Computing

- **■** Faster run time with more compute cores
 - Reduction in an application's execution time, or **speedup**, is the primary goal of parallel computing.
- Larger problem sizes with more compute nodes
 - Exposing parallelism also permits to increase the problem size to be solved, because each node usually has its own memory.
- **■** Energy efficiency by doing more with less
 - Using a larger number of slower but powerefficient cores allows the hardware to return to sleep mode sooner.

Energy = $(No. CPUs) \times (Power/CPU) \times (Hour)$




Importance of Application Parallelism

Seeking Concurrency

- **■** Data Dependence Graphs
 - Vertex
 - a task to be completed
 - Edge from task u to task v
 - Task *u* must be completed before task *v* begins

If there is no edge between *u* and *v*, they are independent and may be performed concurrently.


Parallel execution means multiple tasks are executed **physically at the same time**. Concurrent execution means multiple tasks can be **in progress**, but not necessarily at the same time. **EX) Read and blue tasks of 4 steps are executed.**






29


Parallelism in graphs








Functional Parallelism (Task Parallelism)



No Parallelism??



Laundry (serial version)




Any idea to finish the laundry work earlier? In the past, the machine itself (=clock frequency) had become faster every year, but we cannot expect it now...



Laundry (data parallel)



30 min 40 min 20 min 30 min 40 min 20 min Serial execution takes 180 min for 2 bags.



Data-parallel execution takes 90 min for 2 bags.



Laundry (task parallel)




30 min 40 min 20 min 90 min

Serial execution takes 180 min for laundry and cooking



While one person is doing laundry, another one can do cooking. Independent tasks are done in parallel. Task-parallel execution takes 90 min for doing laundry and cooking.


Laundry (Pipelining)





Parallelization Ratio


Parallelization Ratio α : The ratio of parallel exec.





Increasing n does not mean infinite speedup

Speedup





Parallel Programming



What's Parallel Programming

■ Parallel Programming

- Programming in a language that allows you to explicitly indicate parallel portions of a program.
 - Those portions can run concurrently on different processors
- Why required?
 - Automatic parallelization is difficult, even though there have been many studies on parallelizing compilers.
- OpenMP and MPI
 - Standards for expressing thread-level parallelism and process-level parallelism, respectively.

Accelerators

- Performance characteristics of accelerators are different from those of general-purpose CPUs.
 - Graphics Processing Unit (GPU)
 - NVIDIA Tesla series
 - Originally developed for 3D image rendering
 - Many-core processors
 - Intel Xeon Phi
 - A lot of simple x86 cores
 - Reconfigurable devices
 - Altair FPGA, Xilinx FPGA
 - Programmable circuits

We have to exploit both parallelism and heterogeneity


System performance metrics

Latency

- The execution time for a task (shorter is better).
 - System 1 is better in terms of latency.

Throughput


- The number of tasks per unit time (more is better).
 - System 2 is better in terms of throughput.





Heterogenous Computing

- **■** CPU and GPU are very different processors.
 - Latency-oriented design (=speculative)
 - CPU has a large cache memory and control unit.
 - Throughput-oriented design (=parallel)
 - GPUs devote more hardware resources to ALUs.



41

Latency-oriented features

■ Get ready for future events!


- Cache memory
 - hold data that are likely accessed in the future.
- OoO execution and branch prediction
 - predict the branch target for speculative execution.


Speculation is one of key technologies in CPU.

 But it needs more hardware resources spent for other than ALU.

Cache Memory

- Memory is much slower than CPU
 - Prepare for the future memory accesses





1. Read

Cache

Cache

1. Read

Processor

3. Write

The processing speed is limited by the memory speed.

The processing speed is limited by the cache speed if data are kept in the cache.

The data to be cached are determined based on the locality of reference.



The cache hit ratio is very important for modern processors to achieve high performance. To increase the cache hit ratio, cache memory occupies quite a large area of the chip.

Branch Prediction

If we can predict the branch target, we can speculatively

execute either A or B.

Conditional branch

```
if ( i == 0 )
{
    A;
}
B;
```

```
Loop
```

```
for ( i = 0; i < N; i++ )
{
    A;
}
B;</pre>
```

A is executed N times and then B is executed

There is usually a statistical bias in the branch targets.

Speculative execution by branch prediction is effective to shorten the latency by preventing pipeline stalls, and can be achieved based on the branch history. But it makes the datapath more complicated and significantly increases the hardware cost of each core.

Strategies for High Throughput


■ Many simple cores

- No speculation features
 - Simplicity to increase the number of cores on a chip
- Many tasks (threads) are executed in parallel.
 - The execution of an individual thread may be slow.

■ Many in-flight threads

- When a thread is stalled, another thread is executed to keep every core working (context switch).
 - Memory access latency is hidden by other thread execution.
 - A lot of registers for reducing the context switch overhead.





High Performance Computing

Summary

■ Introduction to HPC (Supercomputing)

- What parallel computing is and why it's growing in importance.
 - Scientific computing and emerging AI and ML
- Where parallelism exists in modern hardware.
 - Modern HPC systems use parallelism at various levels
- Why the amount of application parallelism is important.
 - An application needs to be parallelized well to exploit the system parallelism.
- Software approaches to exploit parallelism.
 - OpenMP thread-level parallelism
 - MPI node-level (process-level) parallelism

