


Module 3: A+ Understanding and Maintenance of Networks

DAY 3:-

Task 1:



The image shows the login page of a ZTE F660 device. The page has a green header with the ZTE logo on the left and 'F660' on the right. Below the header is a light gray background. In the center, there is a green-bordered box containing the text 'Please login to continue...' and a language selector '中文'. Below this, there are two input fields: 'Username' and 'Password'. The 'Username' field has a key icon on the right. To the right of the 'Password' field is a 'Login' button. At the bottom of the page, there is a copyright notice: '©2008-2022 ZTE Corporation. All rights reserved.'


Task 2:

IP Address - 192.168.1.4


Subnet Mask - 255.255.255.0

Default Gateway - 192.168.1.1

Task 3:



The image shows the 'Internet Protocol Version 4 (TCP/IPv4) Properties' window. The 'General' tab is selected. It contains a text box with the following text: 'You can get IP settings assigned automatically if your network supports this capability. Otherwise, you need to ask your network administrator for the appropriate IP settings.' Below this, there are two radio buttons: 'Obtain an IP address automatically' (which is selected) and 'Use the following IP address:'. Below the 'Use the following IP address:' radio button, there are three input fields: 'IP address:', 'Subnet mask:', and 'Default gateway:'. Each field has a placeholder with four asterisks (* * * *).



The image shows a table with IP configuration details. The first row is the selected radio button 'Use the following IP address:'. The second row is 'IP address:' with the value '192 . 168 . 1 . 50'. The third row is 'Subnet mask:' with the value '255 . 255 . 255 . 0'. The fourth row is 'Default gateway:' with the value '192 . 168 . 1 . 1'.

☒ Use the following IP address:	
IP address:	192 . 168 . 1 . 50
Subnet mask:	255 . 255 . 255 . 0
Default gateway:	192 . 168 . 1 . 1

Task 4:

The DHCP Start IP Address and DHCP End IP address should be in the same subnet as the LAN IP.

LAN IP Address

Subnet Mask

Enable DHCP Server ☒

DHCP Start IP Address

DHCP End IP Address

Assign IspDNS ☐

DNS Server1 IP Address

DNS Server2 IP Address

DNS Server3 IP Address

Default Gateway

Lease Time sec

If two devices on the same network are assigned the same IP address, you get what's called an **IP address conflict**, and it causes network problems.

Problems like:

- Both devices may lose network connectivity intermittently, or one device works while the other doesn't.

- Windows/Mac/Linux systems usually pop up an explicit warning like *"Address conflict — another device on the network has the same IP address"*.

- Data meant for one device may get delivered to the other, causing failed connections, dropped packets, or web pages/apps failing to load correctly.
- Sometimes both devices work fine for a while, then randomly disconnect as the network "flip-flops" between which device responds.