Description	Command
. Use In P	airs airs
Boldface	^ <b>PB</b>
Double strike	^PD
Underline	^PS
Strikeout	^PX
Subscript	^ <b>PV</b>
Superscript	$^{PT}$
Italics toggle	^ <b>P</b> Y
Use Alo	ne
Strikeover	^РН
Non-break space	^PO
Phantom space	^PF *1, *2
Phantom rubout	^PG *1, *2
Strikeover line	^P RETURI
Alternate pitch	^PA
Standard pitch	^PN
Print pause	^PC
Begin condensed mode	^PQ
End condensed mode	∧pw
Begin enlarged mode	^PE
End enlarged mode	^PR

Description	Command
Bidirectional printing	.BP *1
Microjustification	.UJ *1
Page offset, left margin	.PO
Character width	.CW *1
Comment (not printed)	.IG or
Conditional page	.CP
Footing	.FO
Heading	.HE
Heading margin	.HM
Footing margin	.FM
Line height	.LH *1
Margin at top	.MT
Margin at bottom	.MB
New page (page break)	.PA
Omit page number	OP.
Page number	.PN
Page number column	.PC
Subscript/superscript roll	.SR *1
Paper length	.PL

- May be entered in file but not useful unless printed with WordStar 3.3.
   Not on menu

CHARACTI	CHARACTER PITCH LINE HEIGHTS				
Pitch (Characters per inch)	Command	Lines Per Inch	Dot Command		
10		6.0	.LH8*		
12	^A	1			

\*Default
Note: A dot command value must be a whole number.

For alphabetical listing of commands, see index in Portable WordStar Reference Manual.

Note: All print features work on most Epson printers. On other printers, some features may not work.



## **PORTABLE WORDSTAR™ COMMAND CARD**

For the EPSON PX-8

For Release 1.0

Copyright © 1984 MicroPro International Corporation. All rights reserved.

MicroPro and WordStar are registered trademarks and Portable WordStar is a trademark of MicroPro International Corporation.



Printed in Japan 84.11-7.5

H8492011-2 Y204990013