




Web Browser

< > URL https://192.168.40.100/frameMonitor.html

Go Stop

Save Configuration Ping Logout Refresh

CISCO

MONITOR

WLANs

CONTROLLER

WIRELESS

SECURITY

MANAGEMENT

COMMANDS

HELP

FEEDBACK

Home

Monitor

Summary

Access Points

Cisco CleanAir

Statistics

CDP

Rogues

Clients

Sleeping Clients

Multicast

Applications

Local Profiling

Controller Summary

Management IP Address	192.168.40.100 , ::/128
Software Version	8.3.111.0
Field Recovery Image Version	7.6.101.1
System Name	WLC
Up Time	2 minutes, 2 seconds
System Time	Tue Mar 24 00:11:28 2026
Redundancy Mode	N/A
Internal Temperature	+31 C
802.11a Network State	Enabled
802.11b/g Network State	Enabled
Local Mobility Group	
CPU(s) Usage	0%
Individual CPU Usage	0%/1%, 0%/0%
Memory Usage	46%
Fan Status	3800 rpm

Access Point Summary

	Total	Up	Down	
802.11a/n/ac Radios	4	4	0	Detail
802.11b/g/n Radios	4	4	0	Detail
Dual-Band Radios	0	0	0	Detail
All APs	4	4	0	Detail

Client Summary

Current Clients	3	Detail
Excluded Clients	0	Detail
Disabled Clients	0	Detail

[View All](#)

Rogue Summary

Active Rogue APs	0	Detail
Active Rogue Clients	0	Detail
Adhoc Rogues	0	Detail
Rogues on Wired Network	0	

Top WLANs

Profile Name	# of Clients
--------------	--------------

Most Recent Traps

[View All](#)

Top Applications

Application Name	Packet Count	Byte Count
------------------	--------------	------------

[View All](#)

FTP-TFTP

Physical

Config

Services

Desktop

Programming

Attributes

SERVICES

HTTP

DHCP

DHCPv6

TFTP

DNS

SYSLOG

AAA

NTP

EMAIL

FTP

IoT

VM Management

Radius EAP

TFTP

Service

On

Off

File

BR-CORE-config

BR-DSW1-config

BR-DSW2-config

HQ-ASW1-config

HQ-ASW2-config

HQ-ASW3-config

HQ-ASW4-config

HQ-CORE-config

HQ-DSW1-config

R1-config

R2-config

R3-config

Remove File

Press RETURN to get started!

User Access Verification

Password:

HQ-CORE>enable

Password:

HQ-CORE#copy running-config startup-config

Destination filename [startup-config]?

Building configuration...

[OK]

HQ-CORE#SH ACC

HQ-CORE#SH ACCess-lists

Extended IP access list WE

10 deny icmp any 10.10.10.0 0.0.0.255

20 deny tcp any 10.10.10.0 0.0.0.255 eq www

30 permit ip any any

HQ-CORE#

```
HQ-DSW1>enable
Password:
HQ-DSW1#copy running-config startup-config
Destination filename [startup-config]?
Building configuration...
[OK]
HQ-DSW1#
00:44:34: %OSPF-5-ADJCHG: Process 1, Nbr 3.3.3.3 on Vlan20 from LOADING to FULL, Loading Done
00:44:39: %OSPF-5-ADJCHG: Process 1, Nbr 3.3.3.3 on Vlan40 from LOADING to FULL, Loading Done
00:44:39: %OSPF-5-ADJCHG: Process 1, Nbr 2.2.2.2 on GigabitEthernet1/0/1 from LOADING to FULL, Loading Done
00:44:39: %OSPF-5-ADJCHG: Process 1, Nbr 3.3.3.3 on Vlan30 from LOADING to FULL, Loading Done
00:44:44: %OSPF-5-ADJCHG: Process 1, Nbr 3.3.3.3 on Vlan10 from LOADING to FULL, Loading Done

?Bad filename
%Error parsing filename (Bad file number)
HQ-DSW1#
?Bad filename
%Error parsing filename (Bad file number)
HQ-DSW1#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route

Gateway of last resort is not set

    10.0.0.0/8 is variably subnetted, 5 subnets, 2 masks
O       10.10.10.0/24 [110/2] via 10.20.20.34, 00:4294967289:4294967241, GigabitEthernet1/0/1
C       10.20.20.32/30 is directly connected, GigabitEthernet1/0/1
O       10.20.20.36/30 [110/2] via 10.20.20.34, 00:4294967289:4294967241, GigabitEthernet1/0/1
O       10.20.20.40/30 [110/6] via 10.20.20.34, 00:4294967289:4294967241, GigabitEthernet1/0/1
O       10.20.20.44/30 [110/6] via 10.20.20.34, 00:4294967289:4294967241, GigabitEthernet1/0/1
O       20.0.0.0/30 is subnetted, 1 subnets
O       20.20.20.0 [110/3] via 10.20.20.34, 00:4294967289:4294967241, GigabitEthernet1/0/1
O       30.0.0.0/30 is subnetted, 1 subnets
O       30.30.30.0 [110/4] via 10.20.20.34, 00:4294967289:4294967241, GigabitEthernet1/0/1
O       105.0.0.0/30 is subnetted, 1 subnets
O       105.100.50.0 [110/2] via 10.20.20.34, 00:4294967289:4294967241, GigabitEthernet1/0/1

HQ-DSW1#Show ip ospf neighbor

Neighbor ID      Pri   State           Dead Time   Address        Interface
2.2.2.2          1     FULL/DR         00:00:35    10.20.20.34    GigabitEthernet1/0/1
3.3.3.3          1     FULL/DR         00:00:35    192.168.30.2   Vlan30
3.3.3.3          1     FULL/DR         00:00:35    192.168.10.2   Vlan10
3.3.3.3          1     FULL/DR         00:00:35    192.168.20.2   Vlan20
3.3.3.3          1     FULL/DR         00:00:35    192.168.40.2   Vlan40
HQ-DSW1#
```

Copy

Paste

```
%HSRP-6-STATECHANGE: Vlan40 Grp 40 state Speak -> Standby
%HSRP-6-STATECHANGE: Vlan30 Grp 30 state Speak -> Standby

User Access Verification

Password:
HQ-DSW2>enable
Password:
HQ-DSW2#copy running-config startup-config
Destination filename [startup-config]?
Building configuration...
[OK]
HQ-DSW2#
%HSRP-6-STATECHANGE: Vlan40 Grp 40 state Standby -> Active

%HSRP-6-STATECHANGE: Vlan20 Grp 20 state Speak -> Standby

00:00:40: %OSPF-5-ADJCHG: Process 1, Nbr 1.1.1.1 on Vlan20 from LOADING to FULL, Loading Done

%HSRP-6-STATECHANGE: Vlan30 Grp 30 state Standby -> Active

00:00:45: %OSPF-5-ADJCHG: Process 1, Nbr 1.1.1.1 on Vlan30 from LOADING to FULL, Loading Done

00:00:45: %OSPF-5-ADJCHG: Process 1, Nbr 1.1.1.1 on Vlan40 from LOADING to FULL, Loading Done

00:00:45: %OSPF-5-ADJCHG: Process 1, Nbr 2.2.2.2 on GigabitEthernet1/0/1 from LOADING to FULL, Loading Done

%HSRP-6-STATECHANGE: Vlan40 Grp 40 state Speak -> Standby

00:00:50: %OSPF-5-ADJCHG: Process 1, Nbr 1.1.1.1 on Vlan10 from LOADING to FULL, Loading Done

%HSRP-6-STATECHANGE: Vlan30 Grp 30 state Speak -> Standby

?Bad filename
%Error parsing filename (Bad file number)
HQ-DSW2#
HQ-DSW2#copy running-config startup-config
Destination filename [startup-config]?
Building configuration...
[OK]
HQ-DSW2#
?Bad filename
%Error parsing filename (Bad file number)
HQ-DSW2#SH STAND
HQ-DSW2#SH STANDby B
HQ-DSW2#SH STANDby Brief
      P indicates configured to preempt.
      |
Interface  Grp  Pri  P State    Active      Standby      Virtual IP
Vl10       10   100   Standby 192.168.10.1 local       192.168.10.10
Vl20       20   100   Standby 192.168.20.1 local       192.168.20.10
Vl30       30   100   Standby 192.168.30.1 local       192.168.30.10
Vl40       40   100   Standby 192.168.40.1 local       192.168.40.10
HQ-DSW2#
```

Copy

Paste

Physical Config **Desktop** Programming Attributes

IP Configuration

✕

Interface

FastEthernet0

▼

IP Configuration



DHCP



Static

IPv4 Address

192.168.10.52

Subnet Mask

255.255.255.0

Default Gateway

192.168.10.10

DNS Server

8.8.8.8

IPv6 Configuration



Automatic



Static

IPv6 Address

Link Local Address

FE80::260:5CFF:FE1D:52D5

Default Gateway

DNS Server

802.1X



Use 802.1X Security

Authentication

MD5

▼

IOS Command Line Interface

Importers, exporters, distributors and users are responsible for compliance with U.S. and local country laws. By using this product you agree to comply with applicable laws and regulations. If you are unable to comply with U.S. and local laws, return this product immediately.

A summary of U.S. laws governing Cisco cryptographic products may be found at:
<http://www.cisco.com/wwl/export/crypto/tool/stqrg.html>

If you require further assistance please contact us by sending email to export@cisco.com.

Cisco CISC02911/K9 (revision 1.0) with 491520K/32768K bytes of memory.
Processor board ID FTX152400KS
3 Gigabit Ethernet interfaces
DRAM configuration is 64 bits wide with parity disabled.
255K bytes of non-volatile configuration memory.
249856K bytes of ATA System CompactFlash 0 (Read/Write)

Press RETURN to get started!

%SYS-6-LOGGINGHOST_STARTSTOP: Logging to host 10.10.10.7 port 514 started - CLI initiated

%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/1, changed state to up

00:44:38: %OSPF-5-ADJCHG: Process 1, Nbr 30.30.30.1 on GigabitEthernet0/0 from LOADING to FULL, Loading Done

User Access Verification

Password:

R1>enable

Password:

R1#copy running-config startup-config

Destination filename [startup-config]?

Building configuration...

[OK]

R1#

00:44:43: %OSPF-5-ADJCHG: Process 1, Nbr 2.2.2.2 on GigabitEthernet0/1 from LOADING to FULL, Loading Done

?Bad filename

%Error parsing filename (Bad file number)

R1#

?Bad filename

%Error parsing filename (Bad file number)

R1#SH NTP

R1#SH NTP S

R1#SH NTP Status

Clock is synchronized, stratum 2, reference is 10.10.10.8

nominal freq is 250.0000 Hz, actual freq is 249.9990 Hz, precision is 2**24

reference time is ED437CD6.000001FC (0:37:42.508 UTC Mon Mar 23 2026)

clock offset is 0.00 msec, root delay is 0.00 msec

root dispersion is 13.86 msec, peer dispersion is 0.12 msec.

loopfilter state is 'CTRL' (Normal Controlled Loop), drift is - 0.000001193 s/s system poll interval is 4, last update was 10 sec ago.

R1#

Copy

Paste

NTP

PhysicalConfigServicesDesktopProgrammingAttributes

SERVICES

HTTP

DHCP

DHCPv6

TFTP

DNS

SYSLOG

AAA

NTP

EMAIL

FTP

IoT

VM Management

Radius EAP

NTP

Service

On

Off

Authentication

Enable

Disable

Key: 0Password:

March 2026

12:38:44AM

Sun	Mon	Tue	Wed	Thu	Fri	Sat
22	23	24	25	26	27	28
1	2	3	4	5	6	7
8	9	10	11	12	13	14
15	16	17	18	19	20	21
22	23	24	25	26	27	28
29	30	31	1	2	3	4

**WLANs****WLANs**

Entries 1 - 4 of 4

▼ **WLANs**

WLANs

▼ **Advanced**

AP Groups

Current Filter:

[\[Change Filter\]](#) [\[Clear Filter\]](#)

Create New ▼

Go

☐	WLAN ID	Type	Profile Name	WLAN SSID	Admin Status	Security Policies	
☐	1	WLAN	IT	IT	Enabled	[WPA2][Auth(PSK)]	Remo
☐	2	WLAN	FIN	FIN	Enabled	[WPA2][Auth(PSK)]	Remo
☐	3	WLAN	ENG	ENG	Enabled	[WPA2][Auth(PSK)]	Remo
☐	4	WLAN	MANGE	MANGE	Enabled	[WPA2][Auth(PSK)]	Remo

**WLANs****AP Groups**

Entries 1 - 5 of 5

[Add Group](#)▼ **WLANs**

WLANs

▼ **Advanced**

AP Groups

AP Group Name**AP Group Description**[ENG](#)[Remove](#)[FIN](#)[Remove](#)[IT](#)[Remove](#)[MANGE](#)[Remove](#)[default-group](#)

A

DHCP

Physical

Config

Services

Desktop

Programming

Attributes

SERVICES

HTTP

DHCP

DHCPv6

TFTP

DNS

SYSLOG

AAA

NTP

EMAIL

FTP

IoT

VM Management

Radius EAP

DHCP

Interface

FastEthernet0

Service

On

Off

Pool Name

serverPool

Default Gateway

0.0.0.0

DNS Server

0.0.0.0

Start IP Address :

10

10

10

0

Subnet Mask:

255

255

255

0

Maximum Number of Users :

512

TFTP Server:

0.0.0.0

WLC Address:

0.0.0.0

Add

Save

Remove

Pool Name	Default Gateway	DNS Server	Start IP Address	Subnet Mask	Max User	TFTP Server	WLC Address
VLAN 10	192.168....	8.8.8.8	192.168....	255.255....	204	0.0.0.0	192.168....
VLAN 20	192.168....	8.8.8.8	192.168....	255.255....	204	0.0.0.0	192.168....
VLAN 30	192.168....	8.8.8.8	192.168....	255.255....	204	0.0.0.0	192.168....
VLAN 40	192.168....	8.8.8.8	192.168....	255.255....	204	0.0.0.0	192.168....
serverPool	0.0.0.0	0.0.0.0	10.10.10.0	255.255....	512	0.0.0.0	0.0.0.0

تم المسح الضوئي بـ CamScanner

SYS LOG

Physical

Config

Services

Desktop

Programming

Attributes

SERVICES

HTTP

DHCP

DHCPv6

TFTP

DNS

SYSLOG

AAA

NTP

EMAIL

FTP

IoT

VM Management

Radius EAP

Syslog

Service

OnOff

	Time	HostName	Message
1		10.10.10.1	00:44:34: %OSPF-5-ADJCH...

Clear Log

```
Press RETURN to get started!

%SYS-6-LOGGINGHOST_STARTSTOP: Logging to host 10.10.10.7 port 514 started - CLI initiated

%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/1, changed state to up

00:44:38: %OSPF-5-ADJCHG: Process 1, Nbr 30.30.30.1 on GigabitEthernet0/0 from LOADING to FULL, Loading Done

User Access Verification

Password:
R1>enable
Password:
R1#copy running-config startup-config
Destination filename [startup-config]?
Building configuration...
[OK]
R1#
00:44:43: %OSPF-5-ADJCHG: Process 1, Nbr 2.2.2.2 on GigabitEthernet0/1 from LOADING to FULL, Loading Done

?Bad filename
%Error parsing filename (Bad file number)
R1#
?Bad filename
%Error parsing filename (Bad file number)
R1#SH NTP
R1#SH NTP S
R1#SH NTP Status
Clock is synchronized, stratum 2, reference is 10.10.10.8
nominal freq is 250.0000 Hz, actual freq is 249.9990 Hz, precision is 2**24
reference time is ED437CD6.000001FC (0:37:42.508 UTC Mon Mar 23 2026)
clock offset is 0.00 msec, root delay is 0.00 msec
root dispersion is 13.86 msec, peer dispersion is 0.12 msec.
loopfilter state is 'CTRL' (Normal Controlled Loop), drift is - 0.000001193 s/s system poll interval is 4, last update was 10 sec ago.
R1#C
R1#CL
R1#CLOC
R1#CLOCK ?
    set Set the time and date
R1#SH C
R1#SH C?
cdp class-map clock controllers crypto
R1#SH CL
R1#SH CLOC
R1#SH CLOCK ?
    detail Display detailed information
    <cr>
R1#SH CLOCK D
R1#SH CLOCK Detail
2:38:12.411 EET Mon Mar 23 2026
Time source is NTP
R1#
```

Copy

Paste