```
09:20:52 DEMOCMGR  MZ390 STARTED USING z390 V1.4.01e ON J2SE 1.6.0_05
AZ390I Copyright 2008 Automated Software Tools Corporation
AZ390I z390 is licensed under GNU General Public License
AZ390I program = soa\demo\DEMOCMGR
AZ390I options = sysmac(w:\work\z390\mac+.)
  syscpy(w:\work\z390\mac+.) SYSMAC(soa\maclib+mac)
External Symbol Definitions
 ESD=0001 LOC=00000000 LEN=00000000 TYPE=CST NAME=$PRIVATE
 ESD=0002 LOC=00000000 LEN=00000460 TYPE=CST NAME=DEMOCMGR
Assembler Listing
000000                    (1/2)1  SOACMGR CLIENT=DEMOCMGR,HOST=*,PORT=3900,SERVICES=((DEMOSUB1,-45,-45,45),(DEMOSUB2,-4,-4,4))
000000                    (2/6)3+********************************************************************
000000                    (2/7)4+* Copyright 2006 Automated Software Tools Corporation        *
000000                    (2/8)5+* This source code is part of z390 assembler/emulator package  *
000000                    (2/9)6+* The z390 package is distributed under GNU general public license  *
000000                    (2/10)7+* Author - Don Higgins                           *
000000                    (2/11)8+* Date   - 12/26/06                         *
000000                    (2/12)9+********************************************************************
000000                    (2/13)10+* 12/28/06 RPI 523 GEN SOURCE CODE FOR SOA CLIENT MSG MANAGER
000000                    (2/14)11+* 01/05/07 RPI 524 ADD MSGTIME FOR SOA CLIENT SERVER APPLICATIONS
000000                    (2/15)12+* 01/22/07 RPI 542 CORRECT R1ADDR FROM GETMAIN FOR BUFFER
000000                    (2/16)13+* 02/21/07 RPI 553 REMOVE TCPIO LMAX AND USE R5 VS R2 FOR LMSG CALC
000000                    (2/17)14+*       AND HANDLE VARIABLE LENGTH MSGS UP TO LMSG
000000                    (2/19)15+********************************************************************
000000                    (2/20)16+* SOACMGR IS DYNAMICALLY CALLED FROM SOASTUB2 STUB WITH NAME/PARMS
000000                    (2/21)17+*
000000                    (2/22)18+*  INPUT PARMS
000000                    (2/23)19+*   1  NAME OF SERVICE TO BE CALLED
000000                    (2/24)20+*   2  PARAMETER LIST ADDRESS
000000                    (2/25)21+*  ACTION
000000                    (2/26)22+*   1  BUILD MSG WITH LENGTH, NAME, AND PARM VALUES
000000                    (2/27)23+*   2  SEND MSG TO SOA SERVER SOASMGR LISTENING FOR SOA MESSAGES
000000                    (2/28)24+*   3  RECEIVE RESPONSE MSG FROM SOASMGR
000000                    (2/29)25+*   4  MOVE UPDATED PARMS FROM MESSAGE TO ADDRESSES IN PARMLIST
000000                    (2/30)26+*   5  RETURN TO CALLER
000000                    (2/31)27+********************************************************************
000000                    (4/43)28=     PUSH PRINT
000000                    (4/52)315=    POP  PRINT
000000                    (13/77)317+DEMOCMGR   CSECT
000000 90ECD00C           (13/167)318+     STM  14,12,12(13)
000004 45FF0068           (13/168)319+     BAL  15,104(15)
```

```
000008 0000000000000000          (13/169)320+      DC    18F'0'
000050 C4C5D4D6C3D4C7D9          (13/170)321+      DC    CL8'DEMOCMGR'
000058 F0F561F2F761F0F8          (13/171)322+      DC    CL8'05/27/08'
000060 F0F94BF2F0404040          (13/172)323+      DC    CL8'09.20'
000068 50FD0008                  (13/173)324+      ST    15,8(13)
00006C 50DF0004                  (13/174)325+      ST    13,4(15)
000070 18DF                      (13/175)326+      LR    13,15
000072                           (13/188)327+      USING DEMOCMGR+8,13
LISTUSE DEMOCMGR ESD=0002 LOC=00000008 LEN=01000 REG=D OFF=00000 LAB=
000072 1821                      (2/34)329+        LR    R2,R1          SAVE PARM LIST FROM SOA STUB CALL
000074 98232000                  (2/36)330+        LM    R2,R3,0(R2)    R2 = A(SVCNAME) R3=A(SVCPLIST)
000078 58330000                  (2/37)331+        L     R3,0(R3)       R3 = USER CALL PARMS FOR SERVICE
00007C 5890D448        000450     (2/38)332+        L     R9,LMAX        R9 = LENGTH OF MSG BUFFER
000080 5840D444        00044C     (2/39)333+        L     R4,AMSG
000084 5540D430        000438     (8/43)335+        CL    R4,=A(0)
000088 4770D0DC        0000E4     (8/46)336+        BC    15-EQ,ZSTR_IF_1
00008C 1819                      (15/27)340+        LR    1,9
00008E 41000002                  (14/130)342+      LA    0,B'10'
000092 0A04                      (14/131)343+      SVC   4 GMAIN R0=(X'02'=31B,X'01'=COND),R1=LEN OUT(R0=L,R1=A)
000094 1841                      (2/42)345+        LR    R4,R1          R4 = ADDRESS MSG BUFFER RPI 542
000096                           (2/43)346+        USING IHAMSG,R4
LISTUSE DEMOCMGR ESD=0002 LOC=00000008 LEN=01000 REG=D OFF=00000 LAB=
LISTUSE IHAMSG   ESD=0003 LOC=00000000 LEN=01000 REG=4 OFF=00000 LAB=
000096 5040D444        00044C     (2/44)347+        ST    R4,AMSG        SAVE BUFFER FOR RE-ENTRY
00009A 41000002                  (16/62)350+       LA    0,2        R0 = TCPIO OP OPEN CLIENT PORT CONN7ECTION
00009E 41E00000                  (16/68)351+       LA    14,0       R14= 0 FOR LOCAL HOST
0000A2 41100F3C                  (16/118)352+      LA    1,3900
0000A6 0A7C                      (16/123)353+      SVC   X'7C' R0=OP(1-5) R1=PORT R14=HOST/MSG R15=LMSG
0000A8 49F0D440        000448     (8/43)356+        CH    R15,=H'0'
0000AC 4780D0DC        0000E4     (8/46)357+        BC    15-NE,ZSTR_IF_2
0000B0 A7150017        0000DE     (17/49)361+       BRAS  1,*+(WTO#0008_EOT-*+1)/2*2
0000B4 00290000C4C5D4D6          (17/50)362+       DC    AL2(WTO#0008_EOT-*,0),C'DEMOCMGR OPEN FAILED HOST=* PORT=3900'
0000DD          0000DD           (17/51)364+WTO#0008_EOT EQU *
0000DE 0A23                      (17/52)365+       SVC   35
0000E0 47F0D31E        000326     (2/48)367+          B  ABORT
0000E4          0000E4           (10/33)370+ZSTR_IF_2 EQU *
0000E4          0000E4           (10/33)375+ZSTR_IF_1 EQU *
0000E4 41000008                  (18/98)380+       LA    0,8 NANOSECONDS - DOUBLE WORD BIT 63 NANO-SEC COUNTER
0000E8 41104004        000004     (18/76)381+       LA    1,MSGTIME
0000EC 0A0B                      (18/81)382+       SVC   11 TIME AND DATE
0000EE D207D4504004    000458 000004  (2/52)384+        MVC   SAVETIME,MSGTIME  SAVE MSGTIME FOR MATCHING SEND/RECV
0000F4 D207400C2000    00000C     (2/53)385+        MVC   MSGNAME,0(R2)   MOVE SERVICE NAME TO MSG
0000FA D2034014D434    000014 00043C  (2/54)386+        MVC   MSGRC,=F'0'     ZERO RETURN CODE FIELD
```

```
000100 41604018          000018   (2/55)387+      LA   R6,MSGPARMS       R6 = ADDRESS FIRST PARM IN BUFFER
000104 A79AFFE8                   (2/56)388+      AHI  R9,-(MSGPARMS-IHAMSG) R9 = REMAINING BYTES FOR PARMS
000108                            (2/57)389+****************************************************************
000108                            (2/58)390+* TEST EACH SERVICE NAME AND IF FOUND,
000108                            (2/59)391+*  1.  BUILD SEND MESSAGE WITH NAME AND PARMS
000108                            (2/60)392+*  2.  WAIT FOR RECEIVED RESPONSE MESSAGE
000108                            (2/61)393+*  3.  UPDATE NON READ ONLY PARMS RETURNED
000108                            (2/62)394+*  4.  EXIT TO CALLER WITH RETURN CODE RETURNED
000108                            (2/63)395+****************************************************************
000108 D5072000D420       000428   (8/43)398+      CLC   0(8,R2),=CL8'DEMOSUB1'
00010E 4770D1EA           0001F2   (8/46)399+      BC   15-EQ,ZSTR_IF_3
000112                            (2/71)401+****************************************************************
000112                            (2/72)402+* BUILD SEND MESSAGE
000112                            (2/73)403+****************************************************************
000112 58830000                   (2/80)404+      L   R8,0(R3)           R1=A(NEXT PARM)
000116 5870D438           000440   (2/94)405+      L   R7,=F'45'
00011A 0E68                       (2/95)406+      MVCL R6,R8              MOVE SEND PARM
00011C 58830004                   (2/80)407+      L   R8,4(R3)           R1=A(NEXT PARM)
000120 5870D438           000440   (2/94)408+      L   R7,=F'45'
000124 0E68                       (2/95)409+      MVCL R6,R8              MOVE SEND PARM
000126 58830008                   (2/80)410+      L   R8,8(R3)           R1=A(NEXT PARM)
00012A 5870D438           000440   (2/94)411+      L   R7,=F'45'
00012E 0E68                       (2/95)412+      MVCL R6,R8              MOVE SEND PARM
000130 1B64                       (2/100)413+      SR   R6,R4
000132 50604000           000000   (2/101)414+      ST   R6,MSGLEN        SET MSG LENGTH
000136                            (2/102)415+****************************************************************
000136                            (2/103)416+* SEND MESSAGE TO SOACMGR SERVER
000136                            (2/104)417+****************************************************************
000136 41000004                   (16/77)420+      LA   0,4        R0 = TCPIO OP SEND MSG VIA PORT CONNECTION
00013A 1B22                       (16/92)421+      SR   2,2    (SVC WILL ISSUE ERROR IF SERVER PORT AND R2=-1)
00013C 0620                       (16/93)422+      BCTR  2,0
00013E 18E4                       (15/27)424+      LR   14,R4
000140 58F04000           000000   (16/108)426+     L   15,MSGLEN
000144 41100F3C                   (16/118)427+     LA   1,3900
000148 0A7C                       (16/123)428+      SVC  X'7C' R0=OP(1-5) R1=PORT R14=HOST/MSG R15=LMSG
00014A 49F0D440           000448   (8/43)431+      CH  R15,=H'0'
00014E 4780D184           00018C   (8/46)432+      BC   15-NE,ZSTR_IF_4
000152 A715001A           000186   (17/49)436+      BRAS  1,*+(WTO#0018_EOT-*+1)/2*2
000156 002F0000C4C5D4D6           (17/50)437+      DC   AL2(WTO#0018_EOT-*,0),C'DEMOCMGR ERROR ON TCPIO SEND MSG - ABORTING'
000185          000185   (17/51)439+WTO#0018_EOT EQU *
000186 0A23                       (17/52)440+      SVC  35
000188 47F0D31E           000326   (2/108)442+            B  ABORT
```

```
00018C              00018C        (10/33)445+ZSTR_IF_4 EQU *
00018C                        (2/110)448+*********************************************************************
00018C                        (2/111)449+* RECEIVE RESPONSE MESSAGE FROM SOACMGR SERVER AND CLOSE PORT
00018C                        (2/112)450+*********************************************************************
00018C 1864                   (2/113)451+        LR   R6,R4
00018E 5870D448        000450 (2/114)452+        L    R7,LMAX
000192 1B88                    (2/115)453+        SR   R8,R8
000194 1B99                    (2/116)454+        SR   R9,R9
000196 0E68                    (2/117)455+        MVCL R6,R8 CLEAR MESSAGE BUFFER
000198 41B00004                (2/118)456+        LA   R11,4      R11 = LENGTH (4 BYTE RECORD LENGTH)
00019C 41E04000        000000 (2/119)457+        LA   R14,IHAMSG  INTO MSG BUFFER
0001A0 45C0D330        000338 (2/120)458+        BAL  R12,READ_VLR_MSG
0001A4 D507400CD420 00000C 000428 (8/43)461+     CLC  MSGNAME,=CL8'DEMOSUB1'
0001AA 4780D1D4        0001DC (8/46)462+      BC   15-NE,ZSTR_IF_5
0001AE A7150014        0001D6 (17/49)466+      BRAS 1,*+(WTO#0022_EOT-*+1)/2*2
0001B2 0023000040C9D5E5        (17/50)467+      DC   AL2(WTO#0022_EOT-*,0),C' INVALID TCPIO RECEIVE MSG NAME'
0001D5          0001D5         (17/51)468+WTO#0022_EOT EQU *
0001D6 0A23                    (17/52)469+      SVC  35
0001D8 47F0D31E        000326 (2/123)471+        B   ABORT
0001DC          0001DC         (10/33)474+ZSTR_IF_5 EQU *
0001DC                        (2/125)477+*********************************************************************
0001DC                        (2/126)478+* UPDATE NON READ ONLY PARMS RETURNED
0001DC                        (2/127)479+*********************************************************************
0001DC 41804018        000018 (2/128)480+        LA   R8,MSGPARMS
0001E0 5890D448        000450 (2/129)481+        L    R9,LMAX
0001E4 58630008                (2/138)482+        L   R6,8(R3)       R6=A(NEXT PARM)
0001E8 5870D438        000440 (2/139)483+        L   R7,=F'45'
0001EC 0E68                    (2/140)484+        MVCL R6,R8              RETURN UPDATED PARM
0001EE 47F0D30A        000312 (2/145)485+        B   EXIT
0001F2          0001F2         (10/33)488+ZSTR_IF_3 EQU *
0001F2 D5072000D428     000430 (8/43)493+      CLC  0(8,R2),=CL8'DEMOSUB2'
0001F8 4770D2D4        0002DC (8/46)494+      BC   15-EQ,ZSTR_IF_6
0001FC                        (2/71)496+*********************************************************************
0001FC                        (2/72)497+* BUILD SEND MESSAGE
0001FC                        (2/73)498+*********************************************************************
0001FC 58830000                (2/80)499+        L    R8,0(R3)        R1=A(NEXT PARM)
000200 5870D43C        000444 (2/94)500+        L    R7,=F'4'
000204 0E68                    (2/95)501+        MVCL R6,R8              MOVE SEND PARM
000206 58830004                (2/80)502+        L   R8,4(R3)        R1=A(NEXT PARM)
00020A 5870D43C        000444 (2/94)503+        L   R7,=F'4'
00020E 0E68                    (2/95)504+        MVCL R6,R8              MOVE SEND PARM
000210 58830008                (2/80)505+        L   R8,8(R3)        R1=A(NEXT PARM)
000214 5870D43C        000444 (2/94)506+        L   R7,=F'4'
```

```
000218 0E68              (2/95)507+          MVCL R6,R8              MOVE SEND PARM
00021A 1B64              (2/100)508+          SR   R6,R4
00021C 50604000   000000 (2/101)509+          ST   R6,MSGLEN         SET MSG LENGTH
000220                   (2/102)510+*************************************************************
000220                   (2/103)511+* SEND MESSAGE TO SOACMGR SERVER
000220                   (2/104)512+*************************************************************
000220 41000004          (16/77)515+          LA   0,4       R0 = TCPIO OP SEND MSG VIA PORT CONNECTION
000224 1B22              (16/92)516+          SR   2,2   (SVC WILL ISSUE ERROR IF SERVER PORT AND R2=-1)
000226 0620              (16/93)517+          BCTR 2,0
000228 18E4              (15/27)519+          LR   14,R4
00022A 58F04000   000000 (16/108)521+          L    15,MSGLEN
00022E 41100F3C          (16/118)522+          LA   1,3900
000232 0A7C              (16/123)523+          SVC  X'7C' R0=OP(1-5) R1=PORT R14=HOST/MSG R15=LMSG
000234 49F0D440   000448 (8/43)526+          CH   R15,=H'0'
000238 4780D26E   000276 (8/46)527+          BC   15-NE,ZSTR_IF_7
00023C A715001A   000270 (17/49)531+          BRAS 1,*+(WTO#0031_EOT-*+1)/2*2
000240 002F0000C4C5D4D6   (17/50)532+          DC   AL2(WTO#0031_EOT-*,0),C'DEMOCMGR ERROR ON TCPIO SEND MSG - ABORTING'
00026F        00026F     (17/51)534+WTO#0031_EOT EQU *
000270 0A23              (17/52)535+          SVC  35
000272 47F0D31E   000326 (2/108)537+          B    ABORT
000276        000276     (10/33)540+ZSTR_IF_7 EQU *
000276                   (2/110)543+*************************************************************
000276                   (2/111)544+* RECEIVE RESPONSE MESSAGE FROM SOACMGR SERVER AND CLOSE PORT
000276                   (2/112)545+*************************************************************
000276 1864              (2/113)546+          LR   R6,R4
000278 5870D448   000450 (2/114)547+          L    R7,LMAX
00027C 1B88              (2/115)548+          SR   R8,R8
00027E 1B99              (2/116)549+          SR   R9,R9
000280 0E68              (2/117)550+          MVCL R6,R8 CLEAR MESSAGE BUFFER
000282 41B00004          (2/118)551+          LA   R11,4    R11 = LENGTH (4 BYTE RECORD LENGTH)
000286 41E04000   000000 (2/119)552+          LA   R14,IHAMSG   INTO MSG BUFFER
00028A 45C0D330   000338 (2/120)553+          BAL  R12,READ_VLR_MSG
00028E D507400CD428 00000C 000430 (8/43)556+   CLC  MSGNAME,=CL8'DEMOSUB2'
000294 4780D2BE   0002C6 (8/46)557+          BC   15-NE,ZSTR_IF_8
000298 A7150014   0002C0 (17/49)561+          BRAS 1,*+(WTO#0035_EOT-*+1)/2*2
00029C 0023000040C9D5E5   (17/50)562+          DC   AL2(WTO#0035_EOT-*,0),C' INVALID TCPIO RECEIVE MSG NAME'
0002BF        0002BF     (17/51)563+WTO#0035_EOT EQU *
0002C0 0A23              (17/52)564+          SVC  35
0002C2 47F0D31E   000326 (2/123)566+          B    ABORT
0002C6        0002C6     (10/33)569+ZSTR_IF_8 EQU *
0002C6                   (2/125)572+*************************************************************
0002C6                   (2/126)573+* UPDATE NON READ ONLY PARMS RETURNED
```

```
0002C6                   (2/127)574+******************************************************************
0002C6 41804018        000018   (2/128)575+          LA    R8,MSGPARMS
0002CA 5890D448        000450   (2/129)576+          L     R9,LMAX
0002CE 58630008                 (2/138)577+          L     R6,8(R3)          R6=A(NEXT PARM)
0002D2 5870D43C        000444   (2/139)578+          L     R7,=F'4'
0002D6 0E68                     (2/140)579+          MVCL R6,R8               RETURN UPDATED PARM
0002D8 47F0D30A        000312   (2/145)580+          B     EXIT
0002DC        0002DC           (10/33)583+ZSTR_IF_6 EQU *
0002DC A7150018        00030C   (17/49)588+          BRAS  1,*+(WTO#0040_EOT-*+1)/2*2
0002E0 002C0000E2D6C1C3         (17/50)589+          DC    AL2(WTO#0040_EOT-*,0),C'SOACMGR SOA SERVICE NOT FOUND = ABORTING'
00030C        00030C           (17/51)591+WTO#0040_EOT EQU *
00030C 0A23                    (17/52)592+          SVC   35
00030E 47F0D31E        000326  (2/150)594+          B     ABORT
000312                        (2/151)595+******************************************************************
000312                        (2/152)596+* EXIT TO CALLER WITH RETURN CODE FROM SERVICE
000312                        (2/153)597+******************************************************************
000312        000312          (2/154)598+EXIT    EQU  *
000312 58F04014        000014  (2/155)599+          L     R15,MSGRC
000316 18FF                   (15/27)602+          LR    15,(15)
000318 58D0D004               (19/50)604+          L     13,4(,13)
00031C 58E0D00C               (19/51)605+          L     14,12(,13)
000320 982CD01C               (19/52)606+          LM    2,12,28(13)
000324 07FE                   (19/53)607+          BR    14
000326                        (19/29)610+ABORT   DS   0H
000326 41F0000C               (19/33)611+          LA    15,12
00032A 58D0D004               (19/50)612+          L     13,4(,13)
00032E 58E0D00C               (19/51)613+          L     14,12(,13)
000332 982CD01C               (19/52)614+          LM    2,12,28(13)
000336 07FE                   (19/53)615+          BR    14
000338                        (2/158)617+******************************************************************
000338                        (2/159)618+* READ VARIABLE LENGTH MSG INTO BUFFER AT R14
000338                        (2/160)619+*  R14 = READ START ADDRESS
000338                        (2/161)620+******************************************************************
000338                        (2/162)621+READ_VLR_MSG DS 0H
000338 50C0D41C        000424  (2/163)622+          ST    R12,VLR_SAVE    SAVE RETURN ACROSS READ_MSG
00033C D703D418D418    000420 000420  (2/164)623+          XC    READ_LEN,READ_LEN ZERO READ_LEN BYTES
000342 58B0D448        000450  (2/165)624+          L     R11,LMAX    MAX LENGTH MESSAGE ALLOWED
000346 45C0D386        00038E  (2/166)625+          BAL   R12,READ_MSG
00034A 18A2                   (2/167)626+          LR    R10,R2    READ REST ENTIRE MSG FROM SAME CONN
00034C        00034C          (5/44)628+ZSTR_DO_1_TEST EQU   *
00034C D503D418D43C    000420 000444  (8/43)630+          CLC   READ_LEN,=F'4'
000352 47B0D352        00035A  (8/46)631+          BC    15-LT,ZSTR_IF_9
000356 47F0D356        00035E  (5/47)633+          B    ZSTR_DO_1_CODE
```

```
00035A              00035A         (10/33)636+ZSTR_IF_9 EQU *
00035A 47F0D362            00036A   (5/49)639+      B   ZSTR_DO_1_END
00035E            00035E         (5/50)640+ZSTR_DO_1_CODE EQU *
00035E 1BB1                 (2/169)642+         SR  R11,R1    REDUCE REMAINING MAX
000360 1AE1                 (2/170)643+         AR  R14,R1    UPDATE READ STARTING ADDR
000362 45C0D386           00038E   (2/171)644+        BAL  R12,READ_MSG
000366 47F0D344           00034C   (5/58)647+      B   ZSTR_DO_1_TEST
00036A            00036A         (5/59)648+ZSTR_DO_1_END EQU *
00036A            00036A         (5/44)652+ZSTR_DO_2_TEST EQU   *
00036A D503D4184000   000420 000000   (8/43)654+      CLC   READ_LEN,MSGLEN
000370 47B0D370           000378   (8/46)655+      BC   15-LT,ZSTR_IF_10
000374 47F0D374           00037C   (5/47)657+         B   ZSTR_DO_2_CODE
000378            000378         (10/33)660+ZSTR_IF_10 EQU *
000378 47F0D380           000388   (5/49)663+      B   ZSTR_DO_2_END
00037C            00037C         (5/50)664+ZSTR_DO_2_CODE EQU *
00037C 1BB1                 (2/174)666+         SR  R11,R1    REDUCE REMAINING MAX
00037E 1AE1                 (2/175)667+         AR  R14,R1    UPDATE READ STARTING ADDR
000380 45C0D386           00038E   (2/176)668+        BAL  R12,READ_MSG
000384 47F0D362           00036A   (5/58)671+      B   ZSTR_DO_2_TEST
000388            000388         (5/59)672+ZSTR_DO_2_END EQU *
000388 58C0D41C           000424   (2/178)675+      L   R12,VLR_SAVE
00038C 07FC                 (2/179)676+        BR  R12
00038E                 (2/180)677+***************************************************************
00038E                 (2/181)678+* READ THE NUMBER OF BYTES AVAILABLE UP TO R11 INTO BUFFER ELSE ABORT
00038E                 (2/182)679+* R11 = MAX LENGTH TO READ
00038E                 (2/183)680+* R14 = READ START ADDRESS
00038E                 (2/184)681+* INCREMENT READ_LEN BY BYTES READ IN R1
00038E                 (2/185)682+***************************************************************
00038E                 (2/186)683+READ_MSG DS   0H
00038E 41000005             (16/80)686+      LA   0,5        R0 = TCPIO OP RECV MSG VIA PORT CONNECTION
000392 1B22                 (16/92)687+      SR   2,2   (SVC WILL ISSUE ERROR IF SERVER PORT AND R2=-1)
000394 0620                 (16/93)688+      BCTR 2,0
000396 18FB                 (15/27)692+      LR   15,R11
000398 41100F3C             (16/118)694+     LA   1,3900
00039C 0A7C                 (16/123)695+      SVC   X'7C' R0=OP(1-5) R1=PORT R14=HOST/MSG R15=LMSG
00039E 49F0D440           000448   (8/43)698+      CH  R15,=H'0'
0003A2 4780D3CE           0003D6   (8/46)699+      BC   15-NE,ZSTR_IF_11
0003A6 A7150015           0003D0   (17/49)703+      BRAS  1,*+(WTO#0060_EOT-*+1)/2*2
0003AA 00260000E3C3D7C9         (17/50)704+      DC   AL2(WTO#0060_EOT-*,0),C'TCPIO ERROR DEMOCMGR RECEIVE RC NZ'
0003D0            0003D0         (17/51)706+WTO#0060_EOT EQU *
0003D0 0A23                 (17/52)707+      SVC   35
0003D2 47F0D31E           000326   (2/190)709+         B  ABORT
```

```
0003D6             0003D6          (10/33)712+ZSTR_IF_11 EQU *
0003D6 4910D440         000448     (8/43)716+     CH   R1,=H'0'
0003DA 4720D40C         000414     (8/46)717+     BC   15-LE,ZSTR_IF_12
0003DE A7150018         00040E     (17/49)721+     BRAS  1,*+(WTO#0064_EOT-*+1)/2*2
0003E2 002C0000E3C3D7C9           (17/50)722+     DC   AL2(WTO#0064_EOT-*,0),C'TCPIO ERROR DEMOCMGR RECEIVE LENGTH <= 0'
00040E             00040E          (17/51)724+WTO#0064_EOT EQU *
00040E 0A23              (17/52)725+     SVC  35
000410 47F0D31E         000326     (2/194)727+     B   ABORT
000414             000414          (10/33)730+ZSTR_IF_12 EQU *
000414 5800D418         000420     (2/196)733+     L   R0,READ_LEN
000418 1A01              (2/197)734+     AR   R0,R1
00041A 5000D418         000420     (2/198)735+     ST   R0,READ_LEN
00041E 07FC              (2/199)736+     BR   R12
000420 00000000          (2/200)737+READ_LEN DC   F'0' BYTES READ BY READ_MSG
000424 00000000          (2/201)738+VLR_SAVE DC   A(0)
000428             (2/202)739+     LTORG
000428 C4C5D4D6E2E4C2F1 =CL8'DEMOSUB1'
000430 C4C5D4D6E2E4C2F2 =CL8'DEMOSUB2'
000438 00000000      =A(0)
00043C 00000000      =F'0'
000440 0000002D      =F'45'
000444 00000004      =F'4'
000448 0000          =H'0'
00044C 00000000          (2/206)740+AMSG   DC   A(0)               ADDRESS OF MSG BUFFER
000450 0000009F          (2/207)741+LMAX   DC   A(MSGPARMS-IHAMSG+135) MAXIMUM LENGTH OF MESSAGE
000454 0000001C          (2/208)742+LMIN   DC   A(MSGPARMS-IHAMSG+4) MINIMUM LENGTH OF MESSAGE
000458 0000000000000000          (2/209)743+SAVETIME DC   XL8'0'
000460             000000     (20/36)745+R0  EQU   0
000460             000001     (20/36)746+R1  EQU   1
000460             000002     (20/36)747+R2  EQU   2
000460             000003     (20/36)748+R3  EQU   3
000460             000004     (20/36)749+R4  EQU   4
000460             000005     (20/36)750+R5  EQU   5
000460             000006     (20/36)751+R6  EQU   6
000460             000007     (20/36)752+R7  EQU   7
000460             000008     (20/36)753+R8  EQU   8
000460             000009     (20/36)754+R9  EQU   9
000460             00000A     (20/36)755+R10  EQU   10
000460             00000B     (20/36)756+R11  EQU   11
000460             00000C     (20/36)757+R12  EQU   12
000460             00000D     (20/36)758+R13  EQU   13
000460             00000E     (20/36)759+R14  EQU   14
000460             00000F     (20/36)760+R15  EQU   15
```

```
000460                    (21/3)763+************************************************************
000460                    (21/4)764+* Copyright 2007 Automated Software Tools Corporation          *
000460                    (21/5)765+* This source code is part of z390 assembler/emulator package    *
000460                    (21/6)766+* The z390 package is distributed under GNU general public license *
000460                    (21/7)767+* Author - Don Higgins                                   *
000460                    (21/8)768+* Date   - 01/01/07                                    *
000000                    (21/13)769+IHAMSG   DSECT
000000                    (21/14)770+MSGLEN   DS    F    TOTAL LENGTH OF MSG = SUM OF PARMS + 24
000004                    (21/15)771+MSGTIME  DS    FL8   NS TIME STAMP
00000C                    (21/16)772+MSGNAME  DS    CL8   NAME OF SERVICE BEING CALLED
000014                    (21/17)773+MSGRC    DS    A    SERVICE RETURN CODE
000018         000018       (21/18)774+MSGPARMS EQU   *
000018                      (1/3)777  END
```

Symbol Table Listing

```
 SYM=$PRIVATE LOC=00000000 LEN=00000000 ESD=0001 TYPE=CST  XREF=295
 SYM=ABORT    LOC=00000326 LEN=00000002 ESD=0002 TYPE=REL  XREF=610 367 442 471 537
  566 594 709 727
 SYM=AMSG     LOC=0000044C LEN=00000004 ESD=0002 TYPE=REL  XREF=740 333 347
 SYM=DEMOCMGR LOC=00000000 LEN=00000460 ESD=0002 TYPE=CST  XREF=317 327
 SYM=E      LOC=00000008 LEN=00000001 ESD=0000 TYPE=ABS  XREF=297
 SYM=EQ     LOC=00000008 LEN=00000001 ESD=0000 TYPE=ABS  XREF=309 336 399 494
 SYM=EXIT    LOC=00000312 LEN=00000001 ESD=0002 TYPE=REL  XREF=598 485 580
 SYM=GE     LOC=0000000B LEN=00000001 ESD=0000 TYPE=ABS  XREF=312
 SYM=GT     LOC=00000002 LEN=00000001 ESD=0000 TYPE=ABS  XREF=310
 SYM=H      LOC=00000002 LEN=00000001 ESD=0000 TYPE=ABS  XREF=295
 SYM=IHAMSG   LOC=00000000 LEN=00000018 ESD=0003 TYPE=DST  XREF=769 346 388 457 552
  741 742
 SYM=L      LOC=00000004 LEN=00000001 ESD=0000 TYPE=ABS  XREF=296
 SYM=LE     LOC=0000000D LEN=00000001 ESD=0000 TYPE=ABS  XREF=313 717
 SYM=LMAX    LOC=00000450 LEN=00000004 ESD=0002 TYPE=REL  XREF=741 332 452 481 547
  576 624
 SYM=LMIN    LOC=00000454 LEN=00000004 ESD=0002 TYPE=REL  XREF=742
 SYM=LT     LOC=00000004 LEN=00000001 ESD=0000 TYPE=ABS  XREF=311 631 655
 SYM=M      LOC=00000004 LEN=00000001 ESD=0000 TYPE=ABS  XREF=303
 SYM=MSGLEN   LOC=00000000 LEN=00000004 ESD=0003 TYPE=REL  XREF=770 414 426 509 521
  654
 SYM=MSGNAME  LOC=0000000C LEN=00000008 ESD=0003 TYPE=REL  XREF=772 385 461 556
 SYM=MSGPARMS LOC=00000018 LEN=00000001 ESD=0003 TYPE=REL  XREF=774 387 388 480 575
  741 742
 SYM=MSGRC    LOC=00000014 LEN=00000004 ESD=0003 TYPE=REL  XREF=773 386 599
```

```
SYM=MSGTIME  LOC=00000004 LEN=00000008 ESD=0003 TYPE=REL  XREF=771 381 384
SYM=NE     LOC=00000007 LEN=00000001 ESD=0000 TYPE=ABS  XREF=300 357 432 462 527
 557 699
SYM=NH     LOC=0000000D LEN=00000001 ESD=0000 TYPE=ABS  XREF=298
SYM=NL     LOC=0000000B LEN=00000001 ESD=0000 TYPE=ABS  XREF=299
SYM=NM     LOC=0000000B LEN=00000001 ESD=0000 TYPE=ABS  XREF=306
SYM=NO     LOC=0000000E LEN=00000001 ESD=0000 TYPE=ABS  XREF=308
SYM=NP     LOC=0000000D LEN=00000001 ESD=0000 TYPE=ABS  XREF=305
SYM=NZ     LOC=00000007 LEN=00000001 ESD=0000 TYPE=ABS  XREF=307
SYM=O      LOC=00000001 LEN=00000001 ESD=0000 TYPE=ABS  XREF=301
SYM=P      LOC=00000002 LEN=00000001 ESD=0000 TYPE=ABS  XREF=302
SYM=R0     LOC=00000000 LEN=00000001 ESD=0000 TYPE=ABS  XREF=745 733 734 735
SYM=R10    LOC=0000000A LEN=00000001 ESD=0000 TYPE=ABS  XREF=755 626
SYM=R1     LOC=00000001 LEN=00000001 ESD=0000 TYPE=ABS  XREF=746 329 345 642 643
 666 667 716 734
SYM=R11    LOC=0000000B LEN=00000001 ESD=0000 TYPE=ABS  XREF=756 456 551 624 642
 666 692
SYM=R12    LOC=0000000C LEN=00000001 ESD=0000 TYPE=ABS  XREF=757 458 553 622 625
 644 668 675 676 736
SYM=R13    LOC=0000000D LEN=00000001 ESD=0000 TYPE=ABS  XREF=758
SYM=R14    LOC=0000000E LEN=00000001 ESD=0000 TYPE=ABS  XREF=759 457 552 643 667
SYM=R15    LOC=0000000F LEN=00000001 ESD=0000 TYPE=ABS  XREF=760 356 431 526 599
 698
SYM=R2     LOC=00000002 LEN=00000001 ESD=0000 TYPE=ABS  XREF=747 329 330 385 398
 493 626
SYM=R3     LOC=00000003 LEN=00000001 ESD=0000 TYPE=ABS  XREF=748 330 331 404 407
 410 482 499 502 505 577
SYM=R4     LOC=00000004 LEN=00000001 ESD=0000 TYPE=ABS  XREF=749 333 335 345 346
 347 413 424 451 508 519 546
SYM=R5     LOC=00000005 LEN=00000001 ESD=0000 TYPE=ABS  XREF=750
SYM=R6     LOC=00000006 LEN=00000001 ESD=0000 TYPE=ABS  XREF=751 387 406 409 412
 413 414 451 455 482 484 501 504 507 508 509 546 550 577 579
SYM=R7     LOC=00000007 LEN=00000001 ESD=0000 TYPE=ABS  XREF=752 405 408 411 452
 483 500 503 506 547 578
SYM=R8     LOC=00000008 LEN=00000001 ESD=0000 TYPE=ABS  XREF=753 404 406 407 409
 410 412 453 455 480 484 499 501 502 504 505 507 548 550 575 579
SYM=R9     LOC=00000009 LEN=00000001 ESD=0000 TYPE=ABS  XREF=754 332 388 454 481
 549 576
SYM=READ_LEN LOC=00000420 LEN=00000004 ESD=0002 TYPE=REL  XREF=737 623 630 654 733
 735
SYM=READ_MSG LOC=0000038E LEN=00000002 ESD=0002 TYPE=REL  XREF=683 625 644 668
SYM=READ_VLR_MSG LOC=00000338 LEN=00000002 ESD=0002 TYPE=REL  XREF=621 458 553
SYM=SAVETIME LOC=00000458 LEN=00000008 ESD=0002 TYPE=REL  XREF=743 384
```

```
SYM=VLR_SAVE LOC=00000424 LEN=00000004 ESD=0002 TYPE=REL  XREF=738 622 675
SYM=WTO#0008_EOT LOC=000000DD LEN=00000001 ESD=0002 TYPE=REL  XREF=364 361 362
SYM=WTO#0018_EOT LOC=00000185 LEN=00000001 ESD=0002 TYPE=REL  XREF=439 436 437
SYM=WTO#0022_EOT LOC=000001D5 LEN=00000001 ESD=0002 TYPE=REL  XREF=468 466 467
SYM=WTO#0031_EOT LOC=0000026F LEN=00000001 ESD=0002 TYPE=REL  XREF=534 531 532
SYM=WTO#0035_EOT LOC=000002BF LEN=00000001 ESD=0002 TYPE=REL  XREF=563 561 562
SYM=WTO#0040_EOT LOC=0000030C LEN=00000001 ESD=0002 TYPE=REL  XREF=591 588 589
SYM=WTO#0060_EOT LOC=000003D0 LEN=00000001 ESD=0002 TYPE=REL  XREF=706 703 704
SYM=WTO#0064_EOT LOC=0000040E LEN=00000001 ESD=0002 TYPE=REL  XREF=724 721 722
SYM=Z       LOC=00000008 LEN=00000001 ESD=0000 TYPE=ABS  XREF=304
SYM=ZSTR_DO_1_CODE LOC=0000035E LEN=00000001 ESD=0002 TYPE=REL  XREF=640 633
SYM=ZSTR_DO_1_END LOC=0000036A LEN=00000001 ESD=0002 TYPE=REL  XREF=648 639
SYM=ZSTR_DO_1_TEST LOC=0000034C LEN=00000001 ESD=0002 TYPE=REL  XREF=628 647
SYM=ZSTR_DO_2_CODE LOC=0000037C LEN=00000001 ESD=0002 TYPE=REL  XREF=664 657
SYM=ZSTR_DO_2_END LOC=00000388 LEN=00000001 ESD=0002 TYPE=REL  XREF=672 663
SYM=ZSTR_DO_2_TEST LOC=0000036A LEN=00000001 ESD=0002 TYPE=REL  XREF=652 671
SYM=ZSTR_IF_10 LOC=00000378 LEN=00000001 ESD=0002 TYPE=REL  XREF=660 655
SYM=ZSTR_IF_1 LOC=000000E4 LEN=00000001 ESD=0002 TYPE=REL  XREF=375 336
SYM=ZSTR_IF_11 LOC=000003D6 LEN=00000001 ESD=0002 TYPE=REL  XREF=712 699
SYM=ZSTR_IF_12 LOC=00000414 LEN=00000001 ESD=0002 TYPE=REL  XREF=730 717
SYM=ZSTR_IF_2 LOC=000000E4 LEN=00000001 ESD=0002 TYPE=REL  XREF=370 357
SYM=ZSTR_IF_3 LOC=000001F2 LEN=00000001 ESD=0002 TYPE=REL  XREF=488 399
SYM=ZSTR_IF_4 LOC=0000018C LEN=00000001 ESD=0002 TYPE=REL  XREF=445 432
SYM=ZSTR_IF_5 LOC=000001DC LEN=00000001 ESD=0002 TYPE=REL  XREF=474 462
SYM=ZSTR_IF_6 LOC=000002DC LEN=00000001 ESD=0002 TYPE=REL  XREF=583 494
SYM=ZSTR_IF_7 LOC=00000276 LEN=00000001 ESD=0002 TYPE=REL  XREF=540 527
SYM=ZSTR_IF_8 LOC=000002C6 LEN=00000001 ESD=0002 TYPE=REL  XREF=569 557
SYM=ZSTR_IF_9 LOC=0000035A LEN=00000001 ESD=0002 TYPE=REL  XREF=636 631


 Literal Table Listing

 LIT=A(0)    LOC=00000438 LEN=00000004 ESD=0002 POOL=0001 XREF=335
 LIT=CL8'DEMOSUB1' LOC=00000428 LEN=00000008 ESD=0002 POOL=0001 XREF=398 461
 LIT=CL8'DEMOSUB2' LOC=00000430 LEN=00000008 ESD=0002 POOL=0001 XREF=493 556
 LIT=F'0'    LOC=0000043C LEN=00000004 ESD=0002 POOL=0001 XREF=386
 LIT=F'4'    LOC=00000444 LEN=00000004 ESD=0002 POOL=0001 XREF=500 503 506 578 630
 LIT=F'45'   LOC=00000440 LEN=00000004 ESD=0002 POOL=0001 XREF=405 408 411 483
 LIT=H'0'    LOC=00000448 LEN=00000002 ESD=0002 POOL=0001 XREF=356 431 526 698 716


 AZ390I total mnote warnings = 0
 AZ390I total mnote errors   = 0
 AZ390I max   mnote level    = 0
```

```
AZ390I total mz390 errors   = 0
AZ390I total az390 errors   = 0
09:20:52 DEMOCMGR  MZ390 ENDED   RC= 0 SEC= 0 MEM(MB)= 40 IO=2037
```