	Properties	Verbs	Parameters	Descriptions
ops/bin/vmdkops_admin.py	Policy	Create	content	The VSAN policy string
			name	The name of the policy
		Rm	name	The name of the policy
		Ls		List policies
		Update	content	The VSAN policy string
			name	The name of the policy
	Volume	ls	vmgroup	Displays volumes for a given vmgroup
			-c	Display selected columns: volume, datastore, vmgroup, capacity, used
		set	volume	Volume to set options for, specified as "volume@datastore".
			options	Options (specifically, access) to be set on the volume.
			vmgroup	Name of the vmgroup the volume belongs to.
	Status			Display vDVS status
			fast	Skip some of the data collection (port, version)
		Rm	name	The name of the vmgroup
				BE CAREFUL: Removes this vmgroup volumes when removing a vmgroup
		Create		The description of the vmgroup
				The name of the vmgroup
				A list of VM names to place in this vmgroup vm1, vm2, vm3,
			default-datastore	Datastore to be used by default for volumes placement
		update	name	The name of the vmgroup
			description	The new description of the vmgroup
				The new name of the vmgroup
				Datastore to be used by default for volumes placement
		Access add	datastore	Datastore which access is controlled
			volume-maxsize	Maximum size of the volume that can be created e.g. 2TB
		Access set	volume-totalsize	Maximum total size of all volume that can be created on the datastore for this vmgroup e.g. 2TB
			name NAME	The name of the vmgroup
		A a a a a a la		Allow create and delete on datastore if set
		Access Is		The name of the vmgroup The name of the vmgroup
ar(Access rm	name datastore	Datastore which access is controlled
š				A list of VM names to rm from this vmgroup
./usr/lib/vmware		Vm rm	name	Vmgroup to remove the VM from
		Vm ls		Vmgroup to list the VMs for
		VIII IS		A list of VM names to replace for this vmgroup
		Vm replace		Vmgroup to replace the VM for
		Vm add		A list of VM names to add to this vmgroup
			name	Vmgroup to add the VM to
		ls		List vmgroups
	config	init	local	Allows local (SingleNode) Init
				Config DB will be placed on a shared datastore
				Force operation, ignore warnings
		status		Display config status
				Where to move the DB to.
		mv	force	Force operation, ignore warnings
		rm		Do not create DB backup before removing
				Explicitly confirm the operation
				Remove only local link or local DB
				Remove the local link to shared DB