

Name: Abrham Abebe

Section: CS2

Email : abrehamabebe1921@gmail.com

From this assignment, I understood how to configure a wireless access point/router and connect wireless clients to a network. First, I learned how to configure the WRS2 router with a static IP address on its Internet interface and configure its LAN IP address. I also learned how to enable DHCP so that wireless clients can automatically receive IP addresses. For wireless configuration, I learned how to set an SSID, hide the SSID broadcast, and secure the wireless network using WPA2-Personal with a password. I also learned how to manually configure a wireless client when the SSID is hidden. Finally, I learned how to verify the connection by checking the IP configuration, signal strength, and using ping to test connectivity between PCs and network devices. This assignment helped me understand how wireless networks work in a real network environment.

Subinterfaces

- G0/0.10 172.17.10.1/24
- G0/0.20 172.17.20.1/24
- G0/0.88 172.17.88.1/24

PC1: 172.17.10.21/24 VLAN 10

PC2: 172.17.20.22/24 VLAN 20

WRS2: 172.17.88.25/24 VLAN 88

PC3: 172.17.40.100/24

PT Activity: 00:19:04

f. Scroll to the bottom of the page and click **Save Settings**.

Part 2: Configure a Wireless Client

Step 1: Configure PC3 for wireless connectivity.

Because SSID broadcast is disabled, you must manually configure **PC3** with the correct SSID and passphrase to establish a connection with the router.

- Click **PC3 > Desktop > PC Wireless**.
- Click the **Profiles** tab.
- Click **New**.
- Name the new profile **Wireless Access**.
- On the next screen, click **Advanced Setup**. Then manually enter the SSID of **WRS_LAN** on **Wireless Network Name**. Click **Next**.
- Choose **Obtain network settings automatically (DHCP)** as the network settings, and then click **Next**.
- On **Wireless Security**, choose **WPA2-Personal** as the method of encryption and click **Next**.
- Enter the passphrase **cisco123** and click **Next**.
- Click **Save** and then click **Connect to Network**.

Step 2: Verify PC3 wireless connectivity and IP addressing configuration.

The **Signal Strength** and **Link Quality** indicators should show that you have a strong signal. Click **More Information** to see details of the connection including IP addressing information. Close the **PC Wireless** configuration window.

Part 3: Verify Connectivity

All the PCs should have connectivity with one another.

Time Elapsed: 00:19:04 Completion: 100/100

☐ Top ☐ Dock 1/1