ACE EXTRACTOR BOT — COMPLETE WORKFLOW

1. USER OPENS BOT

/start
- Welcome
- Help
- Privacy

2. ACCESS ALLOWED?

OWNER-ONLY (default)

PRIVATE / approved

PUBLIC

DENIED / BANNED

/settings

Auto / Media / Document
Custom thumbnail + caption

3A. SINGLE ARCHIVE

ZIP

Send ZIP / RAR / 7Z / TAR...

3B. BULK MODE

/bulk → Send many files → /donebulk

- Supported → FIFO
- Unsupported / oversized → Ignore

4. OWNER DELIVERY?

Choose from reachable users / groups / channels

- YOU, SIR
- MIRROR ONLY
- YOU + MIRROR

Return to sender (for ordinary approved users)

5. SMART FIFO QUEUE

One active archive per user
Process files 1 by 1
Owner sets 1–8 workers
Queue position + /cancel

1 2 3 ...

8. ONE BOTTOM-ANCHORED PROGRESS MESSAGE

% • speed • ETA • elapsed • current file

Moves below every delivered file — no chat flood

6. DOWNLOAD

SECURITY CHECK

Paths • links • size • file count • ratio

PASSWORD?

Ask /password; never log it

EXTRACT

Isolated temp folder

PREPARE MEDIA

- Video thumbnail
- Filename as title
- Split files over 1.95 GB

UPLOAD

- Media + thumbnail
- Retry without thumbnail
- Document fallback

9. FILES DELIVERED

Original filenames
Video thumbnails
To user / mirror / both

PDF

10. LOG + CLEANUP

- Sanitized job details
- Optional original archive copy
- Delete temporary files
- No passwords or secrets

FLOODWAIT

VISIBLE COUNTDOWN

AUTO RETRY

/admin — OWNER CONTROL CENTRE

ACCESS | USERS / BANS | APPEARANCE | LOG CHANNEL | LIMITS / WORKERS | STATS | BROADCAST / RESTART

Customize name, bio, description, welcome image, profile photo, thumbnail and bot behavior inside Telegram

Made by Ace

@Aceddev

Acedevmc@gmail.com