

Table 1

Test Case ID	Title	Description	User Story	Priority	Test Type	Owner/ Author	Environment	Preconditions	Test Data	Steps	Expected Result	Actual Result	Pass/Fail	Notes
TC-001	Add a product to the saved list	Verify that a user can add a product to an initially empty saved list.	As a user, I want to add a product to my empty saved list so that I can start building my shopping list.	High	Positive, Functional, Smoke	Ádám Mészáros	Desktop / Chrome	User is logged in. User has created a saved list named "Shopping List" The "Shopping List" is initially empty.	-	1. Navigate to the ALDI US homepage.	The ALDI US homepage is displayed successfully.			
										2. Select a product category from the left-side menu.	The selected product category page is displayed.			
										3. Select an available product.	The selected product's details page is displayed.			
										4. Click "Add to saved list".	"Shopping List" is displayed under "Save to list"			
										5. Select the list named "Shopping List".	"Shopping List" list is selected.			
										6. Click "Save to list".	"Item saved to shopping list" snack bar displayed.			
										7. Click Back to return to the previous page.	The user returns to the previous page successfully.			
										8. Click the user icon.	The user account menu is displayed.			
										9. Select "Your saved list".	The Your saved list page is displayed and the "Shopping List" is visible. Product details and image are correct. "Show item" button is displayed.			
										10. Click "Show item" under "Shopping List".	The product is displayed in "Shopping List" with the correct product name, details, and image.			
TC-002	Prevent a duplicate product from being added to a saved list	Verify that a product cannot be added to the saved list more than once.	As a user, I want to avoid duplicate products in my saved list so that I can keep my list organized and accurate.	High	Negative, Functional, Smoke	Ádám Mészáros	Desktop / Chrome	User is logged in. User has created a saved list named "Shopping List" The "Shopping List" is initially empty.	-	1. Navigate to the ALDI US homepage.	The ALDI US homepage is displayed successfully.			
										2. Select a product category from the left-side menu.	The selected product category page is displayed.			
										3. Select an available product.	The selected product's details page is displayed.			
										4. Click "Add to saved list".	"Shopping List" is displayed under "Save to list"			
										5. Select the list named "Shopping List".	"Shopping List" list is selected.			
										6. Click "Save to list".	"Item saved to shopping list" snack bar displayed.			
										7. Click Back to return to the previous page.	The user returns to the previous page successfully.			
										8. Select the same product as in step 3				
										9. Click "Add to saved list".	"Shopping List" is displayed under "Save to list", "Shopping list" is checked.			
										10. Make sure "Shopping List is selected.	"Shopping list" is checked.			
										11. Click "Save to list".	"Item saved to shopping list" snack bar is not displayed.			
										12. Click Back to return to the previous page.	The user returns to the previous page successfully.			
										13. Click the user icon.	The user account menu is displayed.			
										14. Select "Your saved list".	Under "Shopping list" selected product is displayed only once.			
										15. Click "Show item" under "Shopping List".	The product is displayed once in "Shopping List" with the correct product name, details, and image.			
TC-003	Remove a product from a saved list	Verify that a user can remove a single product from a saved list containing multiple products.	As a user, I want to remove an unwanted product from my saved list.	High	Positive, Functional, Smoke	Ádám Mészáros	Desktop / Chrome	User is logged in. User has created a saved list named "Shopping List" The "Shopping List" is initially empty.	-	1. Navigate to the ALDI US homepage.	The ALDI US homepage is displayed successfully.			
										2. Select a product category from the left-side menu.	The selected product category page is displayed.			
										3. Select an available product.	The selected product's details page is displayed.			
										4. Click "Add to saved list".	"Shopping List" is displayed under "Save to list"			
										5. Select the list named "Shopping List".	"Shopping List" list is selected.			
										6. Click "Save to list".	"Item saved to shopping list" snack bar displayed.			
										7. Click Back to return to the previous page.	The user returns to the previous page successfully.			
										8. Select a product category from the left-side menu.	The selected product category page is displayed.			
										9. Select an available product.	The selected product's details page is displayed.			
										10. Click "Add to saved list".	"Shopping List" is displayed under "Save to list"			
										11. Select the list named "Shopping List".	"Shopping List" list is selected.			
										12. Click "Save to list".	"Item saved to shopping list" snack bar displayed.			
										13. Click Back to return to the previous page.	The user returns to the previous page successfully.			
										14. Click the user icon.	The user account menu is displayed.			
										15. Select "Your saved list".	The Your saved list page is displayed and the "Shopping List" is visible. Product details and images are correct. "Show all 2 items" button is displayed.			
										16. Click Show all 2 items	The two products are displayed under "Shopping list" along with their details and images.			
										17. Click Manage list	Manage list menu is displayed			
										18. Click remove items	Edit list is displayed with the two products.			
										20. Click the trash can icon next to one of the products.	Item dissapeared.			
										20. Click on Done	Under "Shopping List", only the remaining product is displayed.			
										21. Click Back to return to the previous page.	The user returns to the previous page successfully.			
										22. Click the user icon.	The user account menu is displayed.			
										23. Select "Your saved list".	The Your saved list page is displayed and the "Shopping List" is visible. Product details and image are correct. "Show item" button is displayed.			

Comments

Sheet 1