

Go Long EA Inputs:

The Go Long EA only opens long (buy) positions. It is built for markets that tend to rise over time, such as index CFDs. It opens a position at a set time of day, optionally only once price makes a new daily high, and manages it with configurable stop loss, take profit, break-even and trailing stop.

Trading Volume Modes:

VOLUME_FIXED > Uses a fixed lot size for every trade.

VOLUME_MANAGED > Uses "Fixed Lots" per each "Fixed Lots Per x Money" amount of money in the account.

VOLUME_PERCENT > Lot size is calculated so the set percentage of the account is lost if the initial SL is hit.

VOLUME_MONEY > Lot size is calculated so the set amount of money is lost if the initial SL is hit.

TP / SL Calculation Modes:

CALC_MODE_OFF > No TP/SL is placed.

CALC_MODE_PERCENT > Distance is a percentage of the position open price.

CALC_MODE_POINTS > Distance is set in points (one point = the smallest price change for the symbol).

<General Settings>

Wait For New Day High: If active, a trade is only opened once price makes a new high for the current day.

Trading Volume: Mode used to calculate the lot size for each trade (see Trading Volume Modes above).

Fixed Lots: Lot size for VOLUME_FIXED and VOLUME_MANAGED.

Fixed Lots Per x Money: Base money amount for VOLUME_MANAGED.

Risk Percentage of Balance: Risk percent for VOLUME_PERCENT.

Risk Money: Risk amount for VOLUME_MONEY.

Target Calc Mode: Calculation mode for the take-profit distance (see TP/SL Calculation Modes).

Target Value: Value for the TP calculation based on the Target Calc Mode.

Stop Calc Mode: Calculation mode for the stop-loss distance.

Stop Value: Value for the SL calculation based on the Stop Calc Mode.

<Time Settings>

Trading Start Hour: Hour at which the position is opened (server time).

Trading Start Minute: Minute at which the position is opened.

Close Positions: Decides whether open positions are closed at the close time.

Close Position Hour: Hour at which open positions are closed.

Close Position Minute: Minute at which open positions are closed.

<Trailing Stop Settings>

BE Stop Calc Mode: Calculation mode for the break-even stop.

BE Stop Trigger Value: The break-even stop activates once a trade is more than this value in profit.

BE Stop Buffer Value: How far into profit the stop loss is moved once break-even activates.

TSL Calc Mode: Calculation mode for the classic trailing stop.

TSL Trigger Value: The trailing stop activates once a trade is more than this value in profit.

TSL Value: Distance the trailing stop is kept behind the current market price.

TSL Step Value: The stop loss is only modified if it moves at least this distance.

<More Settings>

Order Comment: Comment attached to every order the EA places.

Magic Number: Unique number identifying this EA's trades. Use a different one for every EA on the same account.

Chart Comment: Activates or deactivates the info comment in the upper-left corner of the chart.

Note: The default inputs are not a recommendation and are not necessarily the best settings. Different symbols require different inputs. Always test in the Strategy Tester and on a demo account first. All the best and good trades :)