### Konfigurasi Core Router

Hostname	Core Router
IP Address	192.168.1.1 (FaO/0)
	192.168.7.1 (Gig9/0)
	192.168.2.1 (Gig7/0)
Subnet mask	255.255.255.0
Gateway	-
DNS Server	192.168.9.53

### Routing Table Core-Router

Network	Netmask	Gateway	Interface	Metric
Destination				
192.168.1.0	-	-	-	-
192.168.7.0				
192.168.2.0				

## Konfigurasi Router 8

Hostname	Router 8	
IP Address	192.168.7.2 (Gig0/0/0)	
	192.168.9.1 (Gig0/0/1)	
Subnet mask	255.255.255.0	
Gateway	-	
DNS Server	192.168.9.53	

### Routing Table Router 8

Network Destination	Netmask	Gateway	Interface	Metric
192.168.7.0	-	-	-	-
192.168.9.0				

### Konfigurasi Distribution Router

Hostname	Distribution Router	
IP Address	192.168.2.2 (Gig6/0)	
	192.168.3.1 (Fa0/0)	
	192.168.4.1 (Fa1/0)	
Subnet mask	255.255.255.0	
Gateway	-	
DNS Server	192.168.9.53	

## Routing Table Distribution Router

Network	Netmask	Gateway	Interface	Metric
Destination				
192.168.2.0	-	-	-	-
192.168.3.0				
192.168.4.0				

## Konfigurasi Access Router A-1

Hostname	Access Router A-1
IP Address	192.168.3.2 (GigO/O)
	192.168.5.1 (GigO/1)
Subnet mask	255.255.255.0
Gateway	-
DNS Server	192.168.9.53

#### Routing Table Access Router A-1

Network	Netmask	Gateway	Interface	Metric
Destination				
192.168.3.0	-	-	-	-
192.168.5.0				

### Konfigurasi Access Router A-2

Hostname	Access Router A-2	
IP Address	192.168.4.2 (Gig0/0)	
	192.168.6.1 (Gig1/0)	
Subnet mask	255.255.255.0	
Gateway	-	
DNS Server	192.168.9.53	

### Routing Table Access Router A-2

Network	Netmask	Gateway	Interface	Metric
Destination				
192.168.4.0	-	-	-	-
192.168.6.0				

### Konfigurasi Main Web Server

Hostname	www.jarkom.org
IP Address	192.168.9.80
Subnet mask	255.255.255.0
Gateway	192.168.9.1
DNS Server	192.168.9.53

#### Konfigurasi DNS Server

Hostname	ns.jarkom.org
IP Address	192.168.9.53
Subnet mask	255.255.255.0
Gateway	192.168.9.1
DNS Server	192.168.9.53

## Konfigurasi DHCP Server A-2

Hostname	dhcp-a2.jarkom.org
IP Address	192.168.6.2
Subnet mask	255.255.255.0
Gateway	192.168.6.1
DNS Server	192.168.9.53

#### Konfigurasi PC0

Hostname	-
IP Address	192.168.5.2
Subnet mask	255.255.255.0
Gateway	192.168.5.1
DNS Server	192.168.9.53

# Konfigurasi PC1

Hostname	-
IP Address	192.168.5.3
Subnet mask	255.255.255.0
Gateway	192.168.5.1
DNS Server	192.168.9.53

# Konfigurasi PC0(2)

Hostname	-
IP Address	192.168.6.5
Subnet mask	255.255.255.0
Gateway	192.168.6.1
DNS Server	192.168.9.53

### Konfigurasi PC1(2)

Hostname	-
IP Address	192.168.6.6
Subnet mask	255.255.255.0
Gateway	192.168.6.1
DNS Server	192.168.9.53

## Konfigurasi AP-1

Hostname	-
IP Address	-
Subnet mask	-
Gateway	-
DNS Server	-
WLAN Security	-
SSID	Wifi 1
SSID Key	12345678

# Konfigurasi AP-2

Hostname	-
IP Address	-
Subnet mask	-
Gateway	-
DNS Server	-
WLAN Security	-
SSID	Wifi 2
SSID Key	12345678