Experiment No. 10

<u>Aim</u>: To Perform File Transfer and Access using FTP using Packet tracer.

<u>Requirements</u>: Windows O.S and Cisco Packet Tracer.

<u>Theory</u>:

What is FTP (File Transfer Protocol)?

FTP (File Transfer Protocol) is a network protocol for transmitting files between computers over Transmission Control Protocol/Internet Protocol (TCP/IP) connections. Within the TCP/IP suite, FTP is considered an application layer protocol. In an FTP transaction, the end user's computer is typically called the local host. The second computer involved in FTP is a remote host, which is usually a server. Both computers need to be connected via a network and configured properly to transfer files via FTP. Servers must be set up to run FTP services, and the client must have FTP software installed to access these services.

How does FTP work?

FTP is a client-server protocol that relies on two communications channels between the client and server: a command channel for controlling the conversation and a data channel for transmitting file content.

Here is how a typical FTP transfer works:

1. A user typically needs to log on to the FTP server, although some servers make some or all of their content available without a login, a model known as anonymous FTP.

2. The client initiates a conversation with the server when the user requests to download a file.

3. Using FTP, a client can upload, download, delete and rename, move and copy files on a server.

<u>Output</u>:

Uploading File (testing.txt) to the server from PC2 using FTP:

```
3    : c1841-ipbase-mz.123-14.T7.bin              13832032
4    : c1841-ipbasek9-mz.124-12.bin               16599160
5    : c1900-universalk9-mz.SPA.155-3.M4a.bin      33591768
6    : c2600-advipservicesk9-mz.124-15.T1.bin      33591768
7    : c2600-i-mz.122-28.bin                       5571584
8    : c2600-ipbasek9-mz.124-8.bin                 13169700
9    : c2800nm-advipservicesk9-mz.124-15.T1.bin    50938004
10   : c2800nm-advipservicesk9-mz.151-4.M4.bin     33591768
11   : c2800nm-ipbase-mz.123-14.T7.bin             5571584
12   : c2800nm-ipbasek9-mz.124-8.bin               15522644
13   : c2900-universalk9-mz.SPA.155-3.M4a.bin      33591768
14   : c2950-i6q4l2-mz.121-22.EA4.bin              3058048
15   : c2950-i6q4l2-mz.121-22.EA8.bin              3117390
16   : c2960-lanbase-mz.122-25.FX.bin              4414921
17   : c2960-lanbase-mz.122-25.SEE1.bin            4670455
18   : c2960-lanbasek9-mz.150-2.SE4.bin            4670455
19   : c3560-advipservicesk9-mz.122-37.SE1.bin     8662192
20   : c3560-advipservicesk9-mz.122-46.SE.bin      10713279
21   : c800-universalk9-mz.SPA.152-4.M4.bin        33591768
22   : c800-universalk9-mz.SPA.154-3.M6a.bin       83029236
23   : cat3k_caa-universalk9.16.03.02.SPA.bin      505532849
24   : cgr1000-universalk9-mz.SPA.154-2.CG         159487552
25   : cgr1000-universalk9-mz.SPA.156-3.CG         184530138
26   : ir800-universalk9-bundle.SPA.156-3.M.bin    160968869
27   : ir800-universalk9-mz.SPA.155-3.M            61750062
28   : ir800-universalk9-mz.SPA.156-3.M            63753767
29   : ir800_yocto-1.7.2.tar                       2877440
30   : ir800_yocto-1.7.2_python-2.7.3.tar          6912000
31   : pt1000-i-mz.122-28.bin                      5571584
32   : pt3000-i6q4l2-mz.121-22.EA4.bin             3117390
33   : testing.txt                                 48
ftp>

C:\>
```

Downloading testing.txt from server to PC0 using FTP:

```
Packet Tracer PC Command Line 1.0
C:\>dir

 Volume in drive C has no label.
 Volume Serial Number is 5E12-4AF3
 Directory of C:\

1/1/1970    5:30 PM           26        sampleFile.txt
               26 bytes            1 File(s)
C:\>ftp 192.168.10.2
Trying to connect...192.168.10.2

%Error ftp://192.168.10.2/ (Ftp peer reset)


 (Disconnecting from ftp server)



ftp 192.168.10.1
Trying to connect...192.168.10.1
Connected to 192.168.10.1
220- Welcome to PT Ftp server
Username:admin
331- Username ok, need password
Password:
230- Logged in
(passive mode On)
ftp>get testing.txt

Reading file testing.txt from 192.168.10.1:
File transfer in progress...
```

Downloading testing.txt from server to PC1 using FTP:

Conclusion: We have successfully access and transfer file from and to the server using FTP command in CISCO Packet tracer.