

Tools

▼ Pinout

 Pinout view

 System view

A->Z

RTC

TIM1

TIM2

TIM3

TIM4

Connectivity

CAN

12C1

SPI1

SPI2

USART1

USART2

④ USART3

USB

12C 12C

Configuration

Reset Configuration

DMA Settings

GPIO Settings

Parameter Settings

👤 User Constants

🔗 NVIC Settings

Configure the below parameters :

 Search (Ctrl+F)

▼ Master Features

I2C Speed Mode	Standard Mode
Standard Mode	Standard Mode
Fast Mode	Standard Mode
Fast Mode Plus	Standard Mode

I2C Clock Speed (Hz) 100000



Tools

▼ Pinout

 System view

USB

12C

```
I2C Clock Speed (Hz) 100000
```



Pinout & Configuration

Clock Configuration

Project Manager

Tools

Software Packs

Pinout

TIM3 Mode and Configuration

Mode

Trigger Source Disable

☒ Internal Clock

Channel1 Disable

Channel2 Disable

Channel3 Disable

Channel4 Disable

Combined Channels Disable

☐ XOR activation

Configuration


Reset Configuration

☒ NVIC Settings☒ DMA Settings☒ Parameter Settings☒ User Constants

NVIC Interrupt Table	Enabled	Preemption Priority	Sub Priority
TIM3 global interrupt	☒	0	0

Pinout view

System view



Pinout & Configuration

Clock Configuration

Project Manager

Tools

Software Packs

Pinout

TIM3 Mode and Configuration

Mode

Trigger Source Disable

☒ Internal Clock

Channel1 Disable

Channel2 Disable

Channel3 Disable

Channel4 Disable

Combined Channels Disable

☐ XOR activation

Configuration

Reset Configuration

☒ NVIC Settings☒ DMA Settings☒ Parameter Settings☒ User Constants

Configure the below parameters :

Search (Ctrl+F)


Prescaler (PSC - 16 bits ... 7199

Counter Mode Up

Counter Period (AutoRelo... 4999

Pinout view

System view



Pinout & Configuration

Clock Configuration

Project Manager

Tools

▼ Software Packs

▼ Pinout

GPIO Mode and Configuration

Configuration

Group By Peripherals

✓ GPIO ✓ I2C ✓ RCC ✓ SYS

Search Signals

Search (Ctrl+F)


☐ Show only Modified Pins

Signal...	Pi...	GPIO...	GPIO...	GPIO ...	Maxim...	User L...	Modified
n/a	PA0-...	Low	Output...	No pul...	Low		☐
n/a	PA1	n/a	Input ...	Pull-up	n/a	pt3	☒
n/a	PA2	n/a	Input ...	Pull-up	n/a	pt2	☒
n/a	PA3	n/a	Input ...	Pull-up	n/a	pt3	☒

Select Pins from table to configure them. Multiple selection is Allowed

Pinout view

System view



Pinout & Configuration

Clock Configuration

Project Manager

Tools

Software Packs

Pinout

Categories

A->Z

System Core >

Analog >

Timers >

Connectivity >

CAN

I2C1

✓ I2C2

SPI1

SPI2

USART1

✗ USART2

✗ USART3

USB

Computing >

Middleware and Software P... >

Pinout view

System view

Middleware

System Core

Analog

Timers

Connectivity

Computing

DMA

GPIO ✓

NVIC ✓

RCC ✓

SYS ✓

TIM3 ✓

I2C2 ✓