Two- and three-point objects

Plain lines expose connectivity. IDs identify recipes; rotated layouts are not extra graph topologies.


I01 Two-point object

`\TwoPointCorr`

Two external segments meet at one marked point.
A central point or optional blob, not a loop correction.

I02 Three-point: upper left


`\ThreePointCorr`



One trivalent vertex; logical slot 1 points upper left.
Four orientations retain the same three logical slots.

I03 Three-point: upper right


`\ThreePointCorr`



One trivalent vertex; logical slot 1 points upper right.
Four orientations retain the same three logical slots.

I04 Three-point: lower left


`\ThreePointCorr`



One trivalent vertex; logical slot 1 points lower left.
Four orientations retain the same three logical slots.

I05 Three-point: lower right

`\ThreePointCorr`




One trivalent vertex; logical slot 1 points lower right.
Four orientations retain the same three logical slots.

Contact and pairing layouts

Pairing presets are shown as implemented. A missing bridge is meaningful, not an omitted annotation.

I06 Central contact


`\FourPointCorr`



Four external edges meet at one quartic vertex.
Connected four-point contact.

I07 Horizontal pairing

`\FourPointCorr`



Top pair and bottom pair each meet separately.
Disconnected pairs; there is no vertical exchange edge.

I08 Vertical pairing


`\FourPointCorr`



Left pair and right pair each meet separately.
Disconnected pairs; there is no horizontal exchange edge.

I09 Crossed contact layout


`\FourPointCorr`



Curved and straight external edges meet at a central point.
The central dot is an interaction, not an over/under crossing.

I10 Flat contact

`\FlatContactCorr`




One quartic vertex with a flat upper pair.
A contact layout, not an additional loop topology.

Tree exchanges and four-legged bubbles

External slot order: 1 upper left, 2 lower left, 3 upper right, 4 lower right. No momentum annotations.

I11 s-channel tree


`\STreeChannelCorr`



Two trivalent vertices joined by one exchange edge.
Bubble/seagull insertions: t-tree leg 1 only.

I12 t-channel tree


`\TTreeChannelCorr`



Two trivalent vertices joined by one exchange edge.
Bubble/seagull insertions: t-tree leg 1 only.

I13 u-channel tree


`\UTreeChannelCorr`



Two trivalent vertices joined by one exchange edge.
Bubble/seagull insertions: t-tree leg 1 only.

I14 s-channel bubble


`\SChannelCorr`



Two quartic vertices joined by two internal edges.
Four-legged bubble already exists; unlike a self-energy insertion.

I15 t-channel bubble


`\TChannelCorr`



Two quartic vertices joined by two internal edges.
Four-legged bubble already exists; unlike a self-energy insertion.

I16 u-channel bubble

`\UChannelCorr`




Two quartic vertices joined by two internal edges.
Four-legged bubble already exists; unlike a self-energy insertion.

Boxes and half-box layouts

The ordinary box already defaults to a square. Half-box presets include identity-specific marker variants.

I17 Square box

`\BoxLoopCorr`




Four trivalent vertices around a single loop.

Default inner spans are both 1.34; explicit overrides remain possible.

I18 Existing crossed box

`\CrossBoxCorr`



Fixed left/right edges plus two crossing diagonals.

No interaction at crossing; internal momentum/index pass is incomplete.

I19 Straight half-box

`\HalfBoxCorr`




Two trivalent vertices with a horizontal bridge.

An open tree helper, despite the half-box name.

I20 Angled half-propagator

`\HalfBoxCorr`




Angled upper stubs on the same two-vertex graph.

A layout variant of the half-box, not a new loop.

I21 Left half-propagator marker

`\HalfBoxCorr`




Angled half-box with the left lower-leg circle preset.

Blank circle retained to show the preset; same underlying graph.

I22 Right half-propagator marker

`\HalfBoxCorr`



Angled half-box with the right lower-leg circle preset.


Blank circle retained to show the preset; same underlying graph.

Four triangle-contact orientations

Two trivalent vertices and one quartic vertex. Independent momentum placement is demonstrated on page 10.

I23 Quartic contact: bottom


`\TriangleContactCorr`



The quartic/contact vertex lies on the bottom side.
Not the regular three-trivalent-vertex triangle attached to a tree.

I24 Quartic contact: top


`\TriangleContactCorr`



The quartic/contact vertex lies on the top side.
Not the regular three-trivalent-vertex triangle attached to a tree.

I25 Quartic contact: left


`\TriangleContactCorr`



The quartic/contact vertex lies on the left side.
Not the regular three-trivalent-vertex triangle attached to a tree.

I26 Quartic contact: right

`\TriangleContactCorr`




The quartic/contact vertex lies on the right side.
Not the regular three-trivalent-vertex triangle attached to a tree.

Loops and the insertion prototype

Bubble and seagull insertions currently support t-tree external slot 1 only. Seagull examples appear on page 8.

I27 Self-energy bubble


`\BubbleCorr`



Two trivalent vertices and two internal arcs; one loop.
Two external legs; distinct from a four-legged channel bubble.

I28 Sunset


`\SunsetDiagram`



Two quartic vertices joined by three internal edges.
Two loops, not a one-loop self-energy bubble.

I29 Bubble on t-tree leg 1

`\TTreeChannelCorr`




A self-energy bubble splits the upper-left external leg.
Only t-tree external slot 1 is implemented; other slots are no-ops.

Existing styles and annotations

Representative combinations, not a promise of every style on every topology. Recipes include all displayed options.

A01 Your pink Proca t-bubble

`\TChannelCorr`




Four double-capped EW legs and two pink Proca internals.

Integrated endpoint checks cover visible contact and legacy overrides.

A02 Polarization and mixed legs

`\ThreePointCorr`




Double cap, single cap, and a pink scalar-polarized leg.

Scalar polarization is a style, not another topology.

A03 EW circles and single caps

`\BoxLoopCorr`




Independent internal particle circles and external endcaps.

Species labels decorate the existing square loop.

A04 Bridge momentum and indices

`\HalfBoxCorr`




A pink bridge with one momentum and endpoint indices.

Omit global line=plain: it overrides the bridge-specific style.

A05 Curved momentum and indices

`\BubbleCorr`




External flow, curved loop momenta, and four endpoint indices.

Representative annotation layout; crowded cases need dedicated checks.

A06 Crossing and Proca circles

`\CrossBoxCorr`



A blank circle on one pink diagonal and a Z on the other.


Crossing stays unconnected; no internal momenta or indices claimed.

Seagull insertion examples

Now supported in this integrated checkout. Only t-tree external slot 1 is implemented; the other legs and s-channel remain future work.

U01 Seagull: bare structure

`\TTreeChannelCorr`




One quartic point on an external leg carries a self-loop.

Supported here: t-tree leg 1 only; other placements remain future work.

U02 Seagull: EW line style

`\TTreeChannelCorr`




The same supported graph with wavy EW propagators.

Supported here: t-tree leg 1 only; other placements remain future work.

S01 One endpoint marker

`\TTreeChannelCorr`




Select proca start on the pink seagull loop.

Loop endpoint selection follows the directed loop path; no caps or circles.

S02 Opposite endpoint marker

`\TTreeChannelCorr`




Select proca end on the pink seagull loop.

Loop endpoint selection follows the directed loop path; no caps or circles.

S03 Both endpoint markers

`\TTreeChannelCorr`



Select proca on the pink seagull loop.


Loop endpoint selection follows the directed loop path; no caps or circles.

Integrated annotation controls

These controls came from the seagull branch. Examples show only the annotation feature being demonstrated.

F01 Compact external indices

`\FourPointCorr`




Compact indices on an empty field base.

Explicit leg labels take precedence over field/index formatting.

F02 Hide external momenta

`\TTreeChannelCorr`




Only the exchange momentum remains; its side label leaves a continuous arrow.

Visibility acts on logical external slots and preserves internal flow.

F03 Blank label versus hidden arrow

`\ThreePointCorr`



Slot 1 has an unlabeled arrow, slot 2 has q, and slot 3 has no arrow.


An empty entry hides text; external-momentum-hide hides the whole arrow.

Independent momentum placement

M02: seven logical slots; per-slot ranges, clearance, label positions and anchors. No new topology.

T01 Annotations: contact bottom


`\TriangleContactCorr`



Slot 2 arrow clearance and slot 6 side label are independent.
Compact quartic-side defaults sit nearer the outer endpoints.

T02 Annotations: contact top


`\TriangleContactCorr`



Slot 5 has its own range; middle arrows face trivalent vertices.
Compact quartic-side defaults sit nearer the outer endpoints.

T03 Annotations: contact left


`\TriangleContactCorr`



Slot 3 uses a continuous arrow with its own side label.
Compact quartic-side defaults sit nearer the outer endpoints.

T04 Annotations: contact right

`\TriangleContactCorr`




Unequal edges retain mixed styles and logical slots.
Compact quartic-side defaults sit nearer the outer endpoints.

Continuous arrows with outside labels

Choose triangle-contact-momentum-layout=side globally, or layout=side for an individual slot.

T05 Side labels: contact bottom


`\TriangleContactCorr`



Continuous arrows; labels sit outward from each edge.
Use layout=gap in an individual slot to mix both modes.

T06 Side labels: contact top


`\TriangleContactCorr`



Continuous arrows; labels sit outward from each edge.
Use layout=gap in an individual slot to mix both modes.

T07 Side labels: contact left


`\TriangleContactCorr`



Continuous arrows; labels sit outward from each edge.
Use layout=gap in an individual slot to mix both modes.

T08 Side labels: contact right

`\TriangleContactCorr`



Continuous arrows; labels sit outward from each edge.
Use layout=gap in an individual slot to mix both modes.