```
Name
                  : icon.asm
 2
 3
     Build
                  : aclocal && autoconf && automake --add-missing --foreign
 4
                    mkdir build
 5
                    cd build
 6
                    ../configure
 7
                    make
 8
9
     Description: a simple window with application icon
10
                  : when copying the application to another location you need to copy the image
11
   file 'logo.png' with it in
12
                    the same directory.
13
14
   ; Source
                  : http://zetcode.com/gui/gtk2/firstprograms/
15
16 bits 64
17
18
  [list -]
19
       extern
                  exit
20
       extern
                  printf
21
       extern
                  gtk_init
22
       extern
                  gtk_window_new
23
       extern
                  gtk_window_set_title
24
       extern
                  gtk_window_set_default_size
25
       extern
                  gtk_window_set_position
26
       extern
                  gtk_window_set_icon
27
       extern
                  gtk_widget_show
28
       extern
                  gtk_main
29
       extern
                  gtk_main_quit
30
       extern
                  g_signal_connect_data
31
       extern
                  gdk_pixbuf_new_from_file
                  GTK_WINDOW_TOPLEVEL
32
       %define
33
                  GTK_WIN_POS_CENTER
       %define
34 [list +]
35
36 section .rodata
37
                        db
       szTitle:
                              "icon",0
38
       szDestroy:
                        db
                              "destroy",0
39
                        db
       szFile:
                              "icon.png",0
                                                                ; must reside in the same directory
40
                              "ERROR loading %s",10,0
       szErrPixbuf:
                        db
41
42 section .data
43
       window:
                        dq
                              0
44
       icon:
                        dq
                              0
45
       pixbuffer:
                        dq
                              0
46
       error:
                        dq
                              0
47
48 section .text
49
       global _start
50
51
   _start:
52
       ;init gtk
53
                rsi,rsi
       xor
                                                          ;argv
54
                rdi,rdi
       xor
                                                          ;argc
55
       call
                gtk init
56
       ;create a new window
                rdi,GTK WINDOW TOPLEVEL
57
       mov
58
       call
                gtk window new
59
       mov
                qword [window],rax
60
       ;set the title
61
       mov
                rdi,qword [window]
62
                rsi,szTitle
       mov
63
       call
                gtk_window_set_title
64
       ;set the size
65
                rdi,qword [window]
       mov
66
                rsi,230
       mov
67
                rdx, 150
       mov
68
                gtk_window_set_default_size
       call
69
       ;set the position
70
                rdi,qword [window]
       mov
71
       mov
                rsi,GTK WIN POS CENTER
72
       call
                gtk window set position
```

```
73
        ;load imagefile in a pixbuffer
 74
        mov
                 rdi, szFile
 75
        mov
                 rsi,error
 76
                 gdk pixbuf new from file
        call
 77
                 qword [pixbuffer], rax
        mov
 78
        and
                 rax, rax
 79
                 .no_icon file error
        jnz
 80
        ;print error to terminal if there was an error
 81
        mov
                 rsi, szFile
82
        mov
                 rdi, szErrPixbuf
83
        xor
                 rax, rax
84
        call
                 printf
85
        jmp
                 .skiploadicon
        ;if no erro then the image is in the pixel buffer
86
87
        ;and we can set the icon
88
   .no icon file error:
89
        mov
                 rdi, qword [window]
90
        mov
                 rsi, qword [pixbuffer]
 91
        call
                 gtk window set icon
 92
   .skiploadicon:
93
        ;connect signal destroy with gtk main quit event handler
94
        xor
                 r9d, r9d
                                            ; combination of GConnectFlags
 95
        xor
                 r8d, r8d
                                            ; a GClosureNotify for data
96
        xor
                 rcx, rcx
                                            ; pointer to the data to pass
 97
        mov
                 rdx,gtk main quit
                                            ; pointer to the handler
98
        mov
                 rsi, szDestroy
                                            ; pointer to the signal
99
        mov
                 rdi, qword[window]
                                           ; pointer to the widget instance
                 g_signal_connect data
100
        call
                                           ; the value in RAX is the handler, but we don't store it
        now
101
        ;show the window
102
        mov
                 rdi, qword [window]
103
        call
                 gtk_widget_show
104
        ;enter process loop
105
        call
                 gtk_main
106
        ;exi program
107
        xor
                 rdi, rdi
108
        call
                 exit
```

109