```
1 ; Name
                  : simple.asm
 2;
 3 ; Build
                  : aclocal && autoconf && automake --add-missing --foreign
4 ;
                   mkdir build
5;
                    cd build
6
                    ../configure
7;
                   make
8
9
  ; Description : a simple window with the basic functionalities and a title
10 ;
11 ; Source
                  : http://zetcode.com/gui/gtk2/firstprograms/
12
13 bits 64
14
15 [list -]
                   GTK WINDOW TOPLEVEL
16
       %define
                                          0
17
       %define
                  GTK WIN POS CENTER
                                          1
                                          0
18
       %define
                  FALSE
19
                                          1
       %define
                  TRUE
20
       extern
                  gtk init
21
       extern
                  gtk main
22
       extern
                  gtk main quit
23
       extern
                  gtk widget show
24
       extern
                  gtk window new
25
       extern
                  gtk window set title
26
       extern
                   g signal connect data
27
       extern
                   exit
28 [list +]
29
30 section .rodata
31
       szTitle:
                      db
                            "simple",0
32
       szDestroy:
                      db
                            "destroy",0
33
34 section .data
35
       window:
                      dq
36
37 section .text
38 global start
39
40 start:
41
       ;init gtk
42
               rdi, rdi
       xor
43
               rsi, rsi
       xor
44
               gtk init
45
       ;if initialization doesn't succeed then the application
46
       ;terminates. If that is unwanted behaviour then we need
47
       ;to use gtk init check instead.
48
       ;https://developer.gnome.org/gtk2/stable/gtk2-General.html#gtk-init
49
       ;create a new window
50
               rdi,GTK WINDOW TOPLEVEL
       mov
51
       call
               gtk window new
52
       mov
               qword[window],rax
53
       ;set the title
54
       mov
               rdi, rax
55
       mov
               rsi,szTitle
56
       call
               gtk window set title
57
       ;connect the destroy signal to gtk main quit event handler
58
               r9d, r9d
                                            ; combination of GConnectFlags
       xor
59
               r8d, r8d
                                            ; a GClosureNotify for data
       xor
60
               rcx,rcx
                                            ; pointer to the data to pass
       xor
61
               rdx,gtk main quit
                                            ; pointer to the handler
       mov
62
                                            ; pointer to the signal
       mov
               rsi,szDestroy
63
               rdi, qword[window]
                                             ; pointer to the widget instance
       mov
64
       ;C programs uses g signal connect, this is not a library
65
       ; function.
66
       call
               g_signal_connect_data
67
       ;show the window
68
               rdi, qwo rd [window]
       mov
69
               gtk widget show
70
       ;go into applications main loop
71
       call
               gtk main
72 .exit:
```

73 ;exit program **xor rdi,rdi call** exit