

Robin Control Lite — Manual

Version 1.0.1 · by conduit.dsp

Robin Control Lite is a free monophonic sampler. Load your samples, play them from any MIDI key, and add subtle per-note variation so repeated hits never sound identical.

1. Install

macOS (11.0 or newer)

1. Download `RobinControlLite-1.0.1.pkg`.
2. Run the installer.
3. Restart your DAW and rescan plugins.

Installs to: - VST3 → `/Library/Audio/Plug-Ins/VST3/` - AU → `/Library/Audio/Plug-Ins/Components/`

Windows (10 or 11)

1. Download `RobinControlLite-1.0.1-setup.exe`.
2. Run the installer.
3. Restart your DAW and rescan plugins.

Installs to: - VST3 → `C:\Program Files\Common Files\VST3\`

2. Quick start

1. **Load samples** — Click **Load Samples** in the header (or the placeholder in the empty pool) and pick your audio files.
 2. **Play** — Press any key on your MIDI controller. Samples play one at a time.
 3. **Shape** — Adjust pitch, tone, and start/end on the main panel.
 4. **Vary** — Set a randomization range below any knob for per-note variation.
 5. **Choose a mode** — Switch between **Series** and **Random** in the header.
-

3. The header

Button	What it does
Load Samples	Add audio files to the pool (adds to existing — does not replace). You can also drag samples straight into the pool from your DAW or the OS file browser (Finder / Explorer).
Save	Save your current settings as a preset.
Trigger	Fire the next sample without a MIDI key.
Panic !	Instantly stop all sound.
About ?	Version and credits.
Series / Random	Choose how samples are picked (see Section 5).

4. The sample pool

- Holds up to **20 samples**.
- Supported formats: **WAV, AIFF, FLAC, OGG, MP3**.
- **Drag and drop** — drop audio files directly into the pool from your DAW or the OS file browser (Finder / Explorer).
- **Speaker icon** — audition a sample through the plugin.
- **Drag** a slot to reorder it.
- **Delete / replace** a slot from its controls.
- **Clear** empties the pool so you can start fresh.

Tip — preview before loading: The Load Samples window is your system's native file picker, which can play audio. - *macOS*: switch to Column view (⌘3), or select a file and press **Space**. - *Windows*: turn on the **Preview pane** in the dialog toolbar.

5. Playback modes

- **Series** — Samples play in order, cycling back to the start (round-robin).

- **Random** — Samples play in random order, with no repeats until every sample in the pool has played once.

Playback is **monophonic**: one sample sounds at a time. Each key triggers the next sample — it does **not** change the pitch.

6. The controls

Control	What it does
Pitch — Semitones	Shift all samples up or down in semitone steps.
Pitch — Fine	Fine-tune in cents.
Tone — Low	Low shelf, ± 12 dB at 250 Hz.
Tone — High	High shelf, ± 12 dB at 4 kHz.
Sample Start	Trim where playback begins.
Sample End	Trim where playback ends.
Amplitude — Volume	Overall output level.
Amplitude — Pan	Position the sound left or right in the stereo field.

Pitch is **global** — it applies to every sample the same way.

7. Per-note randomization

Below each knob is a **dual slider** with two thumbs:

- The **left thumb** sets how far the value can drop (negative range).
- The **right thumb** sets how far it can rise (positive range).

On every note, Robin Control Lite picks a fresh random value within that range. Leave both thumbs at the center for no variation; widen them for more movement.

This is the heart of the plugin: a little randomization on pitch, tone, or start makes footsteps, foley, and percussion sound natural instead of looped.

8. Help

- **Email:** hello@conduitdsp.com
 - **Issues:** report bugs with your DAW, OS, and steps to reproduce.
-

Robin Control Lite is free. VST is a trademark of Steinberg Media Technologies GmbH. Audio Units is a trademark of Apple Inc.