# Semi-Dynamic Session Type Tool for ABS

This tool complements the ABS modeling language with support for session types. It can statically verify ABS models against session types and modifies them to enforce specified behavior, which can not be statically guaranteed.

I developed this tool during my bachelor thesis. Please consult my thesis for more information on the tool. I might link the thesis here at some future point.

### Prerequisites

Please make sure that the following dependencies are available on your system:

- Kotlin compiler version 1.3.50
- Erlang version 22.1
- OpenJDK 11

Furthermore, it is assumed, that the commands in the following sections are executed on the bash shell of a linux system.

# Building:hammer\_and\_wrench:

To build the tool, first, a modified version of ABS has to be downloaded and be built.

```
git clone https://github.com/ahbnr/SessionTypeABS.git
git clone --branch thisDestiny https://github.com/ahbnr/abstools.git
cd abstools/frontend
../gradlew assemble
cd ../../SessionTypeABS
./gradlew shadowJar
chmod +x sdstool
```

The SDS-tool can now be found as an executable .jar file in build/libs. We provide a wrapper script sdstool which can be invoked instead of the JAR file.

#### Tests:clipboard:

```
Issue the command ./gradlew test to run all tests.
```

## Usage

The following command

- statically verifies an ABS model against the given session types
- applies our dynamic enforcement techniques to it
- compiles the modified model to Erlang

```
./sdstool compile [flags] [.abs files] [.st files]
```

With the optional flags, verification or enforcement can be deactivated etc. Use ./sdstool compile --help for further information on them.

After compiling the ABS model, it can be executed like this:

gen/erl/run

#### Other commands:

- ./sdstool printModel [.abs files] [.st files] prints the parts of the given ABS model, which are modified by our dynamic enforcement methods.
- ./sdstool printGlobalTypes [.st files] parses the given session type files and outputs them again.
- ./sdstool printLocalTypes [.st files] prints the local session types projected from the given global ones.

## **Evaluation Scripts**

See evalutation/README.md

#### License

See License.txt. This license only applies to the files belonging to this project, not to abstools or the other libraries being used.

#### Used External Libraries And Tools

- our modified variation of abstools, version 1.8.1
- ANTLR, version 4.7
- picocli, version 4.0.0-beta-2
- Apache Commons IO, version 2.6
- JUnit 5, version 5.5.0
- NuProcess, version 1.2.3