

Web Media Converter

Installation Guide — Standard & Pro (v3.0)



Which version do I have?

This guide covers both editions of the app. They install and run the same way — the only difference is what they convert.

	Standard (Free)	Pro (£19.99)
App name	Web Media Converter	Web Media Converter Pro
Images (PNG, JPG, GIF → WebP)	Yes	Yes
Video (MP4, MOV → WebM)	—	Yes
Mixed image + video batches	—	Yes

You can check which one you have from the app itself: open it and look at the title on the main screen, or the splash screen when it launches.

System requirements

- A Mac with Apple Silicon (M1, M2, M3, or M4). This build does not run on Intel Macs.
- macOS 12 (Monterey) or later.

Step 1 — Install

- 1 Download the **.dmg** file for your version (Standard or Pro).
- 2 Double-click the downloaded **.dmg** to open it.
- 3 Drag the app icon into your **Applications** folder.
- 4 Once copied, eject the mounted disk image (right-click it on the Desktop → Eject), then you can delete the downloaded **.dmg** file.

Step 2 — First launch (macOS security check)

This app is distributed independently, outside the Mac App Store, so the first time you open it macOS will show a security warning. This is expected — it does not mean anything is wrong with the app. Use whichever of the two messages you actually see below.

If you see “[App name] can't be opened because Apple cannot check it for malicious software”

- 1 In **Finder**, go to Applications.

- 2 **Right-click** (or Control-click) the app icon and choose **Open** from the menu — do not just double-click it.
- 3 A dialog will appear with an **Open** button. Click it.
- 4 This confirmation is only needed the first time you launch the app.

If you see “[App name] is damaged and can't be opened”

This message is misleading — it does not mean the download is actually corrupted. It appears because the app isn't notarized by Apple, and macOS marks downloaded files with a quarantine flag that triggers this warning. To clear it:

- 1 Open **Terminal** (Applications → Utilities → Terminal, or search for it with Spotlight).
- 2 Type `xattr -cr` (with a trailing space) — do not press Return yet.
- 3 Drag the app icon from your Applications folder into the Terminal window; this fills in the correct path automatically.
- 4 Press Return, and enter your Mac password if prompted (it won't be visible as you type — that's normal).
- 5 Open the app again — it should now launch normally.

Example of the finished command (yours will show your actual app name):

```
xattr -cr /Applications/Web Media Converter Pro.app
```

Step 3 — Using the app

- 1 Click **Select Files** or **Select Folder** to add images (Pro also accepts video).
- 2 Adjust the WebP quality slider — 85% is a good default for web use. Pro users converting video will also see a WebM bitrate slider once a video file is added.
- 3 Click **Process Files**.
- 4 Once done, download converted files individually or grab them all as a single .zip.

Everything happens on your Mac — files are never uploaded anywhere.

Upgrading from Standard to Pro

The free Standard version converts images only. If you need video conversion too, purchase Pro from davidpaul2.gumroad.com and install it following the same steps above — it installs as a separate app alongside Standard, so you don't need to uninstall anything first.

Support

Questions or issues? Reach out via dpaul.studio, or use the session log inside the app (tap the “!” icon) to copy diagnostic details when reporting a problem.