

Clicking a settings button when there's a slider under the mouse in the next screen plays the click sound twice

[MC-145748](#) SOUND

Status	Resolved / Fixed
Affected	Minecraft 19w11a; Minecraft 19w12b; Minecraft 19w13a; Minecraft 19w13b; Minecraft 19w14a; Minecraft 19w14b; Minecraft 1.14 Pre-Release 1; Minecraft 1.14 Pre-Release 2; Minecraft 1.14 Pre-Release 3; Minecraft 1.14 Pre-Release 4; Minecraft 1.14 Pre-Release 5; Minecraft 1.14 (+more)
Fixed in	22w42a
Reported	2019-03-13
Mojira category	Sound; UI

REPRODUCTION TARGET

- Version:** Minecraft Java Edition 1.19.2, the latest stable release listed as affected in the report; do not use snapshot 22w42a or a later version for this reproduction
- Environment:** Vanilla Minecraft Java Edition client running locally with a mouse or equivalent pointer input and audible game audio. Perform the reproduction entirely in the title-screen and Options interfaces; no world or server is required.

PRECONDITIONS

- Install and select exactly Minecraft Java Edition 1.19.2 in the Minecraft Launcher.
- Use an unmodified client where possible; disable client mods and custom resource packs that replace menus or interface sounds so they do not confound the test.
- Connect an audio output device, unmute the operating-system audio mixer, and set the Minecraft application output to a clearly audible but comfortable level.
- Have a method ready to capture or monitor game audio during the final input sequence.
- Use a mouse or input device that permits the primary button to remain continuously held while the pointer is moved.

STEPS TO REPRODUCE

1 **REPORT**

Start the Minecraft Launcher, select the installation for Java Edition 1.19.2, and launch the game.

SUCCESS CUE Minecraft Java Edition 1.19.2 is running and has reached the main title screen.

2 **INFERRED**

Open the Options screen normally so the in-game volume can be checked before recording the reproduction. Move the pointer to the center of the "Options..." button, press the left mouse button, and release it without dragging the pointer.

INPUT

Left-click "Options..." normally: press and release without moving the mouse while held.

SUCCESS CUE The Options screen is visible, including the FOV slider and the "Music & Sounds..." button.

3 **INFERRED**

Open the sound settings by moving the pointer to "Music & Sounds..." and performing a normal click. Do not begin the test recording yet, because this is only audio preparation.

INPUT Left-click "Music & Sounds..." normally: press and release without dragging.

SUCCESS CUE The Music & Sound Options screen is visible, with the "Master Volume" slider available.

4 **INFERRED**

If Master Volume is muted or too low, move its slider to at least 50%. Click a point at or to the right of the slider's midpoint and release the button at that same point.

INPUT Left-click the midpoint or right half of the "Master Volume" slider.

SUCCESS CUE The displayed Master Volume value is 50% or higher, and game interface audio is not muted.

5 **INFERRED**

Return from Music & Sound Options by normally clicking the "Done" button at the bottom of the screen.

INPUT Left-click "Done" normally.

SUCCESS CUE The general Options screen is visible again.

6 **INFERRED**

Return to the main title screen by normally clicking the "Done" button at the bottom of the Options screen.

INPUT Left-click "Done" normally.

SUCCESS CUE The main title screen is visible and the "Options..." button is available.

7 **INFERRED**

Start game-audio capture, or otherwise begin actively monitoring the game audio. Keep capture running without interruption through the remaining steps.

SUCCESS CUE Audio monitoring or recording is active while the main title screen remains visible.

8 **REPORT**

Move the mouse pointer onto the center of the main title screen's "Options..." button without pressing any mouse button.

INPUT Mouse movement only; do not click yet.

SUCCESS CUE The pointer is over the "Options..." button and the button is visibly highlighted.

9 **REPORT**

Press and continuously hold the left mouse button while the pointer is on "Options...". Do not release the button when the Options screen opens.

INPUT Press and hold the left mouse button; keep it held through steps 10 and 11.

SUCCESS CUE The general Options screen has opened, surrounding menu elements have rendered, and the left mouse button is still physically held down.

10 **REPORT**

While still holding the left mouse button, move the pointer upward onto the FOV slider. Identify this as the horizontal slider near the upper-left portion of the Options screen whose text begins with "FOV:"; use its label rather than relying on exact pixel coordinates.

INPUT

Drag the mouse pointer onto the slider labeled "FOV:" without releasing the left mouse button.

SUCCESS CUE The pointer is inside the rectangular bounds of the FOV slider, the Options screen is fully visible, and the left mouse button remains held.

11 **INFERRED**

Pause pointer movement while keeping the left mouse button held, ensuring the pointer remains over the FOV slider and audio capture remains active.

INPUT Continue holding the left mouse button; do not move the pointer off the FOV slider.

SUCCESS CUE The pointer is stationary over the FOV slider, the button is still held, and the recording includes the complete title-screen-to-Options transition.

12 **REPORT** **TRIGGER**

Release the left mouse button while the pointer remains over the FOV slider. Do not click again or move to another menu immediately afterward.

INPUT Release the held left mouse button over the "FOV:" slider.

SUCCESS CUE The mouse button has been released over the FOV slider, the Options screen remains visible, and the audio capture contains the complete press-drag-release sequence.

HANDOFF TO OBSERVATION

The left mouse button has just been released over the FOV slider after being pressed on the title-screen "Options..." button and held continuously during the menu transition and pointer movement. The Options screen is still visible and audio capture is active or has preserved the entire sequence; hand control to the observation subsystem now.

UNCERTAINTIES

- The report does not prescribe a specific operating system, window resolution, GUI scale, or fixed pixel coordinates. The FOV slider should therefore be located by its visible "FOV:" label.
- The report does not specify an audio volume value. Setting Master Volume to at least 50% is a practical choice solely to make the interface sounds readily observable.
- The report lists many affected versions. This plan selects Java Edition 1.19.2 because it is the latest stable release explicitly listed as affected, while 22w42a is listed as the fix version.
- Custom controls may replace the physical left mouse button, but the required action is the bound primary attack/select mouse action held continuously across the screen transition.

MANUAL RESULT

Version used	
Reproduced?	YES / NO / PARTIAL
Trigger reached?	YES / NO
Crash file	
Notes	
Tested by / date	