

Sprinting isn't canceled when dismounting rideable entities while sprinting

MC-30403 CAMERA

Status	Resolved / Fixed
Affected	Minecraft 13w36a; Minecraft 13w36b; Minecraft 1.7.2; Minecraft 1.7.4; Minecraft 14w02b; Minecraft 14w02c; Minecraft 14w05b; Minecraft 14w06b; Minecraft 14w07a; Minecraft 14w08a; Minecraft 1.7.5; Minecraft 14w11b; Minecraft 1.7.9; Minecraft 1.7.10; Minecraft 14w33c; Minecraft 14w34a (+more)
Fixed in	Minecraft 14w34d; 22w44a; 23w03a
Reported	2013-09-07
Mojira category	Camera

REPRODUCTION TARGET

Use version: Minecraft 13w36a

Affected versions (112):

Minecraft 13w36a	Minecraft 13w36b	Minecraft 1.7.2	Minecraft 1.7.4	Minecraft 14w02b
Minecraft 14w02c	Minecraft 14w05b	Minecraft 14w06b	Minecraft 14w07a	Minecraft 14w08a
Minecraft 1.7.5	Minecraft 14w11b	Minecraft 1.7.9	Minecraft 1.7.10	Minecraft 14w33c
Minecraft 14w34a	Minecraft 14w34b	Minecraft 14w34c	Minecraft 1.8	Minecraft 1.8.1-pre3
Minecraft 15w47c	Minecraft 1.9.1	Minecraft 1.9.2	Minecraft 16w14a	Minecraft 16w32b
Minecraft 1.11	Minecraft 17w06a	Minecraft 1.12.1	Minecraft 1.12.2 Pre-Release 1	
Minecraft 1.12.2 Pre-Release 2	Minecraft 1.12.2	Minecraft 17w43a	Minecraft 17w43b	
Minecraft 17w45a	Minecraft 17w48a	Minecraft 17w50a	Minecraft 18w09a	Minecraft 1.13-pre1
Minecraft 1.13-pre3	Minecraft 1.13-pre6	Minecraft 1.13-pre10	Minecraft 1.13	
Minecraft 18w30b	Minecraft 18w31a	Minecraft 1.13.1	Minecraft 1.13.2-pre2	1.14.4
1.15 Pre-release 3	1.15	1.15.1	1.15.2	20w13b
20w17a	20w18a	20w19a	20w21a	20w22a
1.16 Pre-release 2	1.16 Pre-release 3	1.16 Pre-release 4	1.16 Pre-release 5	
1.16 Pre-release 6	1.16 Pre-release 7	1.16 Pre-release 8	1.16	1.16.1
20w29a	1.16.2			
1.16.3 Release Candidate 1	1.16.3	1.16.4	20w46a	20w51a
21w03a	21w05b	21w06a	21w07a	
21w11a	21w13a	21w14a	21w17a	1.17
1.17.1 Pre-release 1	1.17.1 Pre-release 2			
1.17.1 Pre-release 3	1.17.1 Release Candidate 1	1.17.1	21w38a	21w39a
21w40a	21w41a			
21w42a	1.18 Pre-release 1	1.18 Pre-release 6	1.18	1.18.1
22w03a	22w05a	22w06a	22w07a	
1.18.2 Release Candidate 1	1.18.2	22w14a	22w17a	22w19a
1.19	1.19.1	1.19.2	22w42a	
22w43a	22w44a	22w45a		

Environment: Minecraft Java Edition client running the exact historical snapshot 13w36a. Use a local single-player Creative-mode Superflat world with keyboard and mouse controls. The operational plan assumes the default bindings W for Move Forward, Left Ctrl for Sprint, Left Shift for Sneak/Dismount, E for Inventory, and right-click for Use Item/Interact; if controls are rebound, use the keys currently assigned to those actions. No dedicated server, additional players, commands, cheats, seed, datapack, resource pack, or mod is required.

PRECONDITIONS

- Install or configure a Minecraft Launcher installation for the exact Java Edition snapshot 13w36a; do not use 13w36b, 1.7.2, a fix version, or a modern release for the recommended run.
- Use an unmodified client so that mods do not alter movement, riding, camera FOV, or sprint controls.
- Confirm under Options -> Controls that Move Forward, Sprint, and Sneak are bound and can be pressed simultaneously. With default controls these are W, Left Ctrl, and Left Shift.
- Use the dedicated Sprint action required by the report rather than initiating sprint by double-tapping W.
- Keep the player on the ground. Do not enter Creative flight by double-tapping Space.
- Use an adult pig. A piglet is not suitable because it cannot be saddled and mounted for this procedure.
- Leave at least one hotbar slot empty so the player can mount the pig without holding an item that has another right-click interaction.
- Perform the test in a clear area where the pig and player cannot immediately collide with walls, fall from an edge, enter water, or take damage.

STEPS TO REPRODUCE

1 REPORT

Start the Minecraft Launcher installation configured for the exact snapshot 13w36a and wait for the game to reach its main menu.

INPUT Launch Minecraft Java Edition 13w36a

SUCCESS CUE The main menu is displayed and the lower-left version label identifies 13w36a.

2 INFERRED

Open the single-player world menu and begin creating a new world.

INPUT Singleplayer -> Create New World

SUCCESS CUE The Create New World configuration screen is open.

3 INFERRED

Set the new world's game mode to Creative so the required pig spawn egg and saddle can be obtained without exploration or crafting.

INPUT Click Game Mode until it reads Game Mode: Creative

SUCCESS CUE The world configuration screen shows Creative as the selected game mode.

4 INFERRED

Configure a flat, unobstructed test world. Open the additional world options, cycle the world type to Superflat, and return to the main world-creation screen. Leave the seed unspecified.

INPUT More World Options... -> click World Type until Superflat is selected -> Done

SUCCESS CUE The world-creation screen is configured for Creative mode and the Superflat world type.

5 INFERRED

Create the world.

INPUT Create New World

SUCCESS CUE World generation begins.

6 INFERRED

Wait for world loading to finish before setting up the pig. Do not continue while the terrain is blank, still rapidly appearing, or player input is unresponsive.

SUCCESS CUE The player is standing on the Superflat surface, nearby terrain is rendered, the HUD is visible, and looking or walking responds normally.

7 INFERRED

Open the Creative inventory.

INPUT E

SUCCESS CUE The Creative inventory interface is open and the hotbar is visible at the bottom.

8 **INFERRED**

Locate a pig spawn egg and a saddle in the Creative inventory. If necessary, hover over candidate items and read their tooltips to distinguish the pig egg from other spawn eggs. Place the pig spawn egg in hotbar slot 1, the saddle in hotbar slot 2, and leave hotbar slot 3 empty.

INPUT Pig spawn egg -> hotbar slot 1; Saddle -> hotbar slot 2; hotbar slot 3 left empty

SUCCESS CUE Hotbar slot 1 contains a pig spawn egg, slot 2 contains a saddle, and slot 3 is empty.

9 **INFERRED**

Close the inventory and return to first-person world control.

INPUT E

SUCCESS CUE The inventory closes and the crosshair is visible in the world.

10 **INFERRED**

Select hotbar slot 1, aim the crosshair at an unobstructed ground block a few blocks away, and use the pig spawn egg. Verify that the spawned pig is full-sized; if a piglet is produced, spawn another pig on an empty ground block and use an adult for the remaining steps.

INPUT Press 1, then right-click the ground

SUCCESS CUE A full-sized adult pig is standing on the flat ground within interaction range.

11 **VERIFIED**

Select the saddle, aim directly at the adult pig, and use the saddle on it once.

INPUT Press 2, then right-click the adult pig

SUCCESS CUE The pig visibly wears a saddle and remains available to mount.

12 **VERIFIED**

Switch to the empty hotbar slot so no held item interferes with interaction. Aim directly at the saddled pig and interact with it to mount.

INPUT Press 3, then right-click the saddled pig

SUCCESS CUE The viewpoint moves onto the pig, the player is seated on it, and the on-screen prompt indicates that the Sneak control can be used to dismount if that prompt is present in this version.

13 **VERIFIED**

While remaining mounted, press and hold Move Forward, then press and continue holding the dedicated Sprint key. Do not initiate sprint by double-tapping forward. Keep both inputs depressed until the next step. The pig does not need to be steered with a carrot on a stick for this state transition.

INPUT Hold W, then hold Left Ctrl without releasing W

SUCCESS CUE The player remains mounted on the saddled pig with both Move Forward and Sprint inputs held; the camera FOV has shifted from its idle view, confirming that the sprint input registered.

14 **REPORT** **TRIGGER**

Without releasing Move Forward or Sprint, press the Sneak/Dismount control once to leave the pig.

INPUT While still holding W + Left Ctrl, press Left Shift once

SUCCESS CUE The player is no longer seated on the pig and is positioned beside or near it; W and Left Ctrl have not yet been released.

15 **REPORT**

Immediately release both Move Forward and Sprint, and do not press Sprint again. Allow any short forward movement caused by the held keys to stop, without mounting another entity, opening a menu, attacking, or changing game mode.

INPUT Release W and Left Ctrl

SUCCESS CUE The player is dismounted, no movement or sprint input is being held, ordinary movement has slowed to a stop, and the camera view is unobstructed and ready for inspection.

HANDOFF TO OBSERVATION

The player has just dismounted the saddled pig while Move Forward and the dedicated Sprint key were held, then released both inputs and slowed to a stop without pressing Sprint again. Begin observing the player's camera/FOV and sprint-state indicators before any further movement or sprint input changes the state.

UNCERTAINTIES

- The report does not specify game mode, world type, world seed, single-player versus multiplayer, or server configuration. A local Creative-mode Superflat world is selected only as the simplest deterministic way to obtain and mount a pig.
- The report lists 22w44a both as an affected version and as a fix version. It is preserved in `affected_versions` because the report explicitly lists it there, but it is not selected as the recommended reproduction version.
- The historical Creative inventory may label the pig spawn egg as 'Spawn Pig' rather than using modern item-name wording. The executor should identify it by the pig-related tooltip and egg appearance rather than depending on one exact UI label.
- The report's later stop-and-restart-sprinting sequence is a post-trigger comparison performed after inspecting the initial state. It is not included beyond the first trigger because this plan hands control to the Observation Agent immediately after the dismount-and-slow-down state is established.
- External verification was limited to operational controls and pig interaction details because those details were necessary to turn the report's high-level mounting, sprinting, and dismounting instructions into executable inputs for the historical version.

MANUAL RESULT

Version used	
Reproduced?	YES / NO / PARTIAL
Trigger reached?	YES / NO
Crash file	
Notes	
Tested by / date	