

The main hand is positioned incorrectly when holding a loaded crossbow in your offhand

[MC-227169](#) PLAYER ANIMATION

Status	Resolved / Fixed
Affected	1.17 Pre-release 4; 1.17 Release Candidate 1; 1.17; 1.17.1; 21w39a; 1.18 Pre-release 6; 1.18.1; 1.18.2; 22w11a; 1.19; 1.19.1 Release Candidate 2; 1.19.1; 1.19.2; 22w42a; 1.19.3; 1.20.1; 1.20.2; 1.20.4; 24w06a; 24w09a; 1.20.6; 24w21b; 1.21 Pre-Release 4; 24w36a
Fixed in	24w33a
Reported	2021-06-02
Mojira category	Player Animation

REPRODUCTION TARGET

Use version: 1.17 Pre-release 4

Affected versions (24):

1.17 Pre-release 4

1.17 Release Candidate 1

1.17

1.17.1

21w39a

1.18 Pre-release 6

1.18.1

1.18.2

22w11a

1.19

1.19.1 Release Candidate 2

1.19.1

1.19.2

22w42a

1.19.3

1.20.1

1.20.2

1.20.4

24w06a

24w09a

1.20.6

24w21b

1.21 Pre-Release 4

24w36a

Environment: Minecraft Java Edition 1.17 Pre-release 4 in a local single-player world. Use Creative mode as a deterministic way to obtain the crossbow and arrow. Perform the reproduction in first-person view. No specific world seed, coordinates, server, graphics setting, or multiplayer configuration is required by the report.

PRECONDITIONS

- Launch the exact affected version 1.17 Pre-release 4 rather than the listed fix version.
- Use a newly created or existing world in which the player can obtain a crossbow and at least one arrow; the plan uses a new Creative-mode world for convenience.
- Begin with the offhand slot empty.
- Use the configured equivalents if the default controls E (Inventory), F (Swap Item With Offhand), F5 (Change Perspective), or right mouse button (Use Item/Place Block) have been rebound.

STEPS TO REPRODUCE

1 REPORT

In the Minecraft Launcher, select or create an installation that uses exactly Java Edition version 1.17 Pre-release 4, and launch it.

INPUT

Minecraft Launcher -> Installations -> select/create an installation for "1.17 Pre-release 4" -> Play

SUCCESS CUE The Minecraft title screen has loaded and identifies the running version as 1.17 Pre-release 4.

2 INFERRED

Open Singleplayer and create a world in Creative mode. No particular seed or world-generation setting is needed. Enter the world and wait until nearby terrain has rendered and movement responds normally.

INPUT Singleplayer -> Create New World -> Game Mode: Creative -> Create New World

SUCCESS CUE The player is standing in a loaded world in Creative mode, with normal movement and camera response.

3 INFERRED

Set the camera to first-person view. Press the Change Perspective control repeatedly if necessary; its default key is F5.

INPUT F5, repeated only until first-person view is active

SUCCESS CUE The camera looks directly from the player's viewpoint rather than showing the player's full character model in front of or behind the camera.

4 INFERRED

Open the Creative inventory using the Inventory control, whose default key is E.

INPUT E

SUCCESS CUE The Creative inventory interface is open.

5 INFERRED

Use the Creative inventory's Search Items tab to find a Crossbow. Place one Crossbow into an otherwise empty hotbar slot. The hotbar is the nine-slot row shown at the bottom of the screen. Remember which numbered slot, from 1 through 9, received the Crossbow.

INPUT Search Items -> enter "crossbow" -> move one Crossbow to an empty hotbar slot

SUCCESS CUE One Crossbow is present in a known hotbar slot.

6 INFERRED

Search for an Arrow and place at least one Arrow in the inventory or in a different hotbar slot. Do not replace the Crossbow, and do not put the Arrow in the hotbar slot containing the Crossbow.

INPUT

Search Items -> replace the search text with "arrow" -> move at least one Arrow to a different slot

SUCCESS CUE The inventory contains a Crossbow and at least one Arrow in separate slots.

7 **INFERRED**

Close the inventory, then select the hotbar slot containing the Crossbow by pressing its number key or scrolling to it. Confirm that the offhand is still empty before continuing.

INPUT E, then the number key 1–9 corresponding to the Crossbow's hotbar slot

SUCCESS CUE The Crossbow is selected and visible in the main hand, at least one Arrow remains elsewhere in the inventory, and the offhand is empty.

8 **REPORT**

Move the Crossbow from the main hand to the offhand using the Swap Item With Offhand control, whose default key is F. Because the offhand was empty, the selected main-hand hotbar slot becomes empty.

INPUT F

SUCCESS CUE The Crossbow is visible on the offhand side of the first-person view, while the currently selected main-hand hotbar slot is empty.

9 **REPORT**

Begin charging the offhand Crossbow by pressing and holding the Use Item/Place Block control, whose default input is the right mouse button. Keep holding it; do not release during the initial drawing animation.

INPUT Press and hold Right Mouse Button

SUCCESS CUE The offhand Crossbow is undergoing its drawing/loading animation, and the right mouse button remains held.

10 **REPORT** **TRIGGER**

Continue holding the right mouse button until the Crossbow finishes drawing and its loading sound sequence completes. Then release the right mouse button so that the Crossbow remains charged in the offhand. Do not swap hands, select another hotbar slot, fire the Crossbow, or leave first-person view after releasing the button.

INPUT Release Right Mouse Button only after the Crossbow has fully charged

SUCCESS CUE A loaded Crossbow remains equipped in the offhand, the selected main-hand slot remains empty, and the camera remains in first-person view.

HANDOFF TO OBSERVATION

The player has just released the Use Item control after fully charging the Crossbow. The loaded Crossbow is equipped in the offhand, the selected main-hand hotbar slot is empty, and first-person view remains active. Hand control to the observation subsystem without firing the Crossbow or changing either hand's equipment.

UNCERTAINTIES

- The report does not specify a game mode, world type, seed, or acquisition method. A new Creative-mode single-player world is used only as the simplest deterministic way to obtain the required items.
- The report says to watch how the main hand is displayed but does not explicitly name the camera perspective. First-person view is selected because it directly exposes the rendered hand model being inspected.
- The report does not require a dedicated server, additional players, particular coordinates, a particular main-hand preference, or special graphics settings; none are added to the reproduction requirements.

MANUAL RESULT

Version used	
Reproduced?	YES / NO / PARTIAL
Trigger reached?	YES / NO
Crash file	
Notes	
Tested by / date	