

The player model in the inventory screen renders in the wrong orientation when it's not standing up straight

MC-2791 PLAYER

Status	Resolved / Fixed
Affected	Minecraft 1.4.2; Minecraft 1.4.4; Snapshot 13w10b; Minecraft 1.5; Snapshot 13w11a; Minecraft 1.5.1; Snapshot 13w16a; Snapshot 13w16b; Minecraft 1.5.2; Snapshot 13w17a; Snapshot 13w18a; Snapshot 13w18b; Snapshot 13w19a; Snapshot 13w21a; Snapshot 13w21b; Snapshot 13w22a; Snapshot 13w23a (+more)
Fixed in	25w44a
Reported	2012-11-11
Mojira category	Player; Rendering

REPRODUCTION TARGET

Use version: Minecraft 15w41b

Affected versions (89):

Minecraft 1.4.2

Minecraft 1.4.4

Snapshot 13w10b

Minecraft 1.5

Snapshot 13w11a

Minecraft 1.5.1

Snapshot 13w16a

Snapshot 13w16b

Minecraft 1.5.2

Snapshot 13w17a

Snapshot 13w18a

Snapshot 13w18b

Snapshot 13w19a

Snapshot 13w21a

Snapshot 13w21b

Snapshot 13w22a

Snapshot 13w23a

Snapshot 13w23b

Snapshot 13w24a

Snapshot 13w24b

Snapshot 13w25a

Snapshot 13w25b

Snapshot 13w26a

Minecraft 1.6

Minecraft 1.6.1

Minecraft 1.6.2

Minecraft 1.6.4

Minecraft 13w38a

Minecraft 13w38b

Minecraft 13w38c

Minecraft 1.7.4

Minecraft 14w03b

Minecraft 14w05b

Minecraft 14w06b

Minecraft 14w07a

Minecraft 14w08a

Minecraft 1.7.5

Minecraft 14w11b

Minecraft 14w20b

Minecraft 14w21a

Minecraft 14w21b

Minecraft 1.8

Minecraft 1.8.1-pre3

Minecraft 15w41b

Minecraft 15w49a

Minecraft 1.10.2

Minecraft 16w32a

Minecraft 16w32b

Minecraft 16w33a

Minecraft 16w35a

Minecraft 1.11.2

Minecraft 17w06a

Minecraft 1.12 Pre-Release 5

Minecraft 1.12.2

Minecraft 17w50a

Minecraft 18w01a

Minecraft 18w02a

Minecraft 1.13.1

19w39a

1.15.2

20w07a

20w19a

1.16.1

20w29a

20w30a

1.16.2 Pre-release 1

1.16.4

20w48a

20w49a

20w51a

21w03a

1.16.5

21w05b

21w06a

21w07a

21w11a

21w15a

21w17a

1.17

21w37a

1.19.2

22w45a

1.19.3

1.19.4

23w14a

1.20.1

1.20.2

1.20.4

24w34a

Environment: Vanilla Minecraft Java Edition snapshot 15w41b in a new single-player world, using a keyboard and mouse. Create the world in Creative mode with commands/cheats available, obtain and equip an Elytra, then change to Survival mode while airborne so the normal Survival inventory player-model panel can be opened during an Elytra glide. Use full-screen mode to provide clear far-left and far-right cursor positions. Do not use fix version 25w44a.

PRECONDITIONS

- The launcher must be configured to make historical Java Edition snapshots available and must have a working installation for snapshot 15w41b.
- Use an unmodified client without gameplay, rendering, inventory, or player-animation mods. Disable shaders and custom resource packs unless the report is being separately tested for compatibility.
- Use a new disposable world; no world seed or coordinates are required by the report.
- Use the configured control for Jump, default Space; Inventory, default E; Chat, default T; and Debug Screen, default F3. If controls are rebound, use the actions corresponding to those bindings.
- The world must permit commands so that the player can change from Creative mode to Survival mode after obtaining the Elytra and gaining altitude.
- Leave the chest armor slot empty before equipping the Elytra.

STEPS TO REPRODUCE

1 **REPORT**

Start the Minecraft Java Edition installation for snapshot 15w41b. On the main menu, verify that the displayed version is 15w41b rather than an earlier affected version or fix version 25w44a.

SUCCESS CUE The 15w41b main menu is displayed and identifies the running client as snapshot 15w41b.

2 **INFERRED**

Select Singleplayer, choose Create New World, set Game Mode to Creative, and ensure commands or cheats are allowed. No particular seed or world type is required. Create the world.

SUCCESS CUE A new Creative-mode single-player world begins loading.

3 **INFERRED**

Wait without performing the test until the terrain around the player has rendered and movement responds normally.

SUCCESS CUE Nearby terrain is visible, chunks are no longer visibly appearing around the spawn area, and the player responds normally to movement input.

4 **REPORT**

Switch Minecraft to full-screen mode. Use the Fullscreen control in the video settings if the operating system intercepts the default shortcut.

INPUT F11

SUCCESS CUE The Minecraft window occupies the full display and has distinct far-left and far-right screen edges available for cursor movement.

5 **INFERRED**

Open the Creative inventory using the Inventory control.

INPUT E

SUCCESS CUE The Creative inventory interface is open.

6 **INFERRED**

Open the Creative inventory search tab, select its search field, and search for the Elytra. Left-click the Elytra result and place one Elytra into an empty hotbar slot; the hotbar is the row of nine item slots along the bottom of the interface.

INPUT elytra

SUCCESS CUE One Elytra is present in a hotbar slot.

7 **REPORT**

Open the Survival Inventory section of the Creative inventory—the section containing the player model, crafting grid, main inventory, and four armor slots. Drag the Elytra from the hotbar into the chest armor slot, which is the second armor slot from the top beside the player model.

SUCCESS CUE The Elytra icon occupies the chest armor slot and the player is wearing it rather than carrying it only in the hotbar.

8 **INFERRED**

Close the inventory and return to first-person world control.

INPUT **E**

SUCCESS CUE The world view is active and the inventory interface is closed.

9 **REPORT**

Open the debug screen and rotate horizontally until its facing-direction information says the player is facing south, toward positive Z. This direction is selected because the report comments identify southward Elytra flight as a particularly clear orientation case.

INPUT **F3**

SUCCESS CUE The debug screen reports that the player is facing south or toward positive Z.

10 **VERIFIED**

Start Creative flight by double-pressing the Jump control. While flying, hold Jump to ascend. Continue ascending until the debug screen shows a Y coordinate of at least 180, leaving enough height to open and inspect the inventory during the subsequent glide.

INPUT **Space, Space; then hold Space**

SUCCESS CUE The player is hovering in Creative flight at Y=180 or higher, with the ground well below.

11 **INFERRED**

Release Jump while remaining in Creative flight. Reconfirm that the player is facing south, aim slightly downward so forward motion will descend gradually, and then close the debug screen without changing direction.

INPUT **F3**

SUCCESS CUE The normal world view is visible, the player is hovering high above the terrain, and the view remains directed generally south with a slight downward pitch.

12 **VERIFIED**

Open in-game chat, type the historical version-compatible game-mode command exactly as shown with the leading slash, and press Enter. Execute it in chat, not in a server console.

INPUT **/gamemode survival**

SUCCESS CUE Chat reports a successful game-mode change, the Survival hearts and hunger HUD are present, and the airborne player begins falling.

13 **VERIFIED**

As soon as the player is descending, press the Jump control once to deploy the equipped Elytra. Aim slightly below the horizon and hold Forward, default W, to establish a southward glide. Do not double-press Jump, because the player is now in Survival mode.

INPUT **Space; then hold W**

SUCCESS CUE The motion changes from a near-vertical fall to sustained forward gliding with a shallower descent, and the player remains well above the ground.

14 **REPORT**

While the Elytra glide is still active and before approaching the ground, release movement controls and open the normal Survival inventory using the Inventory control. Opening this interface does not require landing first.

INPUT **E**

SUCCESS CUE The Survival inventory is open, its player-model panel is visible, and the world continues running while the airborne glide state remains active.

15 **REPORT**

Move the mouse cursor to the far-left side of the full-screen Minecraft display, keeping it within the game interface. Pause only long enough to establish the cursor position; do not close the inventory.

SUCCESS CUE The cursor is positioned at the far-left side of the display while the inventory and player-model panel remain open.

16 **REPORT** **TRIGGER**

In one continuous horizontal motion, move the mouse cursor from the far-left side across the inventory and player-model area to the far-right side of the full-screen display. Do not click, close the inventory, land, or repeat the trigger before handing off.

SUCCESS CUE The cursor has just reached the far-right side after crossing from left to right, and the inventory player-model panel remains open during the Elytra glide.

HANDOFF TO OBSERVATION

The Survival inventory is open while the player remains in an active southward Elytra glide, and the mouse cursor has just been moved once from the far-left side to the far-right side of the full-screen display. Begin observation of the inventory player model immediately, before the player lands or the inventory closes.

UNCERTAINTIES

- The first listed affected version is Minecraft 1.4.2, but the report's current Steps to Reproduce require an Elytra. Elytra were introduced in snapshot 15w41a, so the current Elytra procedure cannot be executed in Minecraft 1.4.2. Minecraft 15w41b is therefore selected as the earliest listed affected version that supports the report's current procedure.
- The earliest affected versions correspond to the ticket's historical death/dying inventory reproduction, which the report says ceased to be usable when the inventory began closing on death. This plan intentionally follows only the report's current Elytra reproduction path.
- The report does not require a specific game mode, seed, coordinate, altitude, or world type. Starting in Creative mode, ascending to Y=180 or higher, and changing to Survival mode while airborne are practical choices that remove item-acquisition and tower-building randomness without changing the Elytra inventory condition.
- Full-screen mode is used because the report explicitly discusses cursor behavior at the left and right sides of a full-screen display, although it also indicates that cursor movement across a windowed Minecraft display may be sufficient.
- Southward flight is selected from a report comment describing it as a particularly clear orientation case. The main Steps to Reproduce do not state that southward travel is mandatory.

MANUAL RESULT

Version used	
Reproduced?	YES / NO / PARTIAL
Trigger reached?	YES / NO
Crash file	
Notes	
Tested by / date	