

# When beacon power level is changed, the GUI doesn't update until closed and reopened

MC-1429 Beacon

|          |                                                                                                                  |
|----------|------------------------------------------------------------------------------------------------------------------|
| Status   | Resolved / Fixed                                                                                                 |
| Affected | Minecraft 1.4.2, Snapshot 13w04a, Minecraft 1.6.2, Minecraft 1.7.4, Minecraft 14w02c, Minecraft 1.7.5 (+30 more) |
| Fixed in | 21w20a                                                                                                           |
| Reported | 2012-10-31                                                                                                       |

## STEPS TO REPRODUCE

1. Place the `mc-1429` structure file in `.minecraft\saves\<world\_name>\generated\minecraft\structures`.
2. Open the corresponding world in Creative mode.
3. Run `/setblock ~ ~ ~ structure\_block{mode:"LOAD",name:"mc-1429",showboundingbox:1}`.
4. Obtain an iron ingot.
5. Stand on the pressure plate.
6. Open the beacon GUI and place the iron ingot in the beacon.
7. Leave the pressure plate and wait until the beacon is deactivated.
8. Observe that the open beacon GUI still allows an effect to be selected.

## OBSERVED BEHAVIOUR

## Actual behavior

While the beacon GUI is open, it does not refresh when the beacon becomes inactive or its available power level changes. In the reproduction, stepping off the pressure plate deactivates the beacon, but the already-open GUI continues to display the beacon's previous active state and its effect buttons remain selectable.

Closing and reopening the GUI updates it to reflect the beacon's current state. The issue is limited to the stale GUI state; the beacon itself has already been deactivated.

## EXPECTED BEHAVIOUR

When the beacon's power level or active state changes while its GUI is open, the interface should update immediately to reflect the beacon's current status. If the beacon becomes deactivated, its effect options should no longer be selectable, and the controls should accurately show that no powers are available without requiring the GUI to be closed and reopened.

## ENVIRONMENT

Minecraft Java Edition Versions: 1.4.2, 13w04a, 1.6.2, 1.7.4, 14w02c, 1.7.5, 14w10c, 1.7.10, 14w30b, 14w30c, 14w32a, 1.8, 1.8.1, 1.8.3, 1.8.4, 1.8.6, 15w36d, 15w42a, 16w02a, 1.10, 1.10.1, 1.10.2, 16w32a, 16w32b, 16w33a, 16w35a, 17w06a, 1.12.2, 18w22c, 1.15.2, 20w21a, 1.16.1, 20w29a, 1.16.3, 1.19.3, 23w04a (includes snapshots)

## ORIGINAL DESCRIPTION

## The bug

An open beacon GUI does not update whenever beacon power level or active state changes.

## How to reproduce

- Place this structure file in .minecraft\saves\<world\_name>\generated\minecraft\structures.

- Go in that world and run:

```
/setblock ~ ~ ~ structure_block{mode:"LOAD",name:"mc-1429",showboundingbox:1}
```

- Get an iron ingot, stand on the pressure plate and put the iron in the beacon.

→ After the beacon is deactivated, you can still select an effect

## MANUAL RESULT

|                  |                    |
|------------------|--------------------|
| Version used     |                    |
| Reproduced?      | YES / NO / PARTIAL |
| Crash file       |                    |
| Notes            |                    |
|                  |                    |
| Tested by / date |                    |

Live issue: <https://bugs.mojang.com/browse/MC/issues/MC-1429>