Report about lab2

1-lab2 with startup.s

Sections of learn-in-depth-cortex-m3.elf

```
arm-none-eabi-objdump.exe -h learn_in_depth_cortex_m3.elf
                                   file format elf32-littlearm
learn_in_depth_cortex_m3.elf:
Sections:
                                                  File off
                                                             Algn
Idx Name
                  Size
                                        LMA
 0 .text
                  00000104
                             08000000
                                        08000000
                                                  00008000
                  CONTENTS,
                             ALLOC, LOAD, READONLY, CODE
 1 .data
                  00000004
                             20000000
                                       08000104
                                                  00010000
                                                             2**2
                  CONTENTS, ALLOC, LOAD, DATA
  2 .debug_info
                             00000000
                                                  00010004
                                                             2**0
                  0000013b
                                       00000000
                  CONTENTS,
                             READONLY,
                                       DEBUGGING
  3 .debug_abbrev 000000de
                             00000000
                                        00000000
                                                  0001013f
                                                             2**0
                             READONLY,
                  CONTENTS,
                                       DEBUGGING
 4 .debug_loc
                  00000038
                             00000000
                                                  0001021d
                                       00000000
                             READONLY,
                  CONTENTS.
                                       DEBUGGING
   .debug_aranges 00000020
                              00000000
                                        00000000
                                                   00010255
                                                              2**0
                  CONTENTS,
                             READONLY,
                                       DEBUGGING
  6 .debug_line
                  00000056
                             00000000
                                       00000000
                                                  00010275
                             READONLY,
                  CONTENTS,
                                       DEBUGGING
    .debug_str
                  000000e9
                             00000000
                                       00000000
                                                  000102cb
                                                             2**0
                  CONTENTS,
                             READONLY,
                                       DEBUGGING
    .comment
                  00000011
                             00000000
                                        00000000
                                                  000103b4
                  CONTENTS,
                             READONLY
    .ARM.attributes 00000033
                               00000000
                                          00000000
                                                    000103c5
                                                               2**0
                  CONTENTS, READONLY
 10 .debug_frame
                  0000002c
                             00000000
                                        00000000
                                                  000103f8
                  CONTENTS, READONLY, DEBUGGING
```

Symbols of learn-in-depth-cortex-m3.elf

2-lab2 with startup.c

Sections of learn-in-depth-cortex-m3.elf

```
arm-none-eabi-objdump.exe -h learn_in_depth_cortex_m3.elf
learn_in_depth_cortex_m3.elf:
                                  file format elf32-littlearm
Sections:
Idx Name
                  Size
                                                 File off
                            VMA
                                      I MA
                  00000180
                            08000000
                                      08000000
                                                 000080000
 0 .text
                  CONTENTS,
                            ALLOC, LOAD, READONLY, CODE
 1 .data
                  00000004
                            20000000 08000180
                                                 00010000
                  CONTENTS,
                            ALLOC, LOAD, DATA
 2 .bss
                  00001000
                            20000004
                                      08000184
                                                 00010004
                                                           2**0
                  ALLOC
  3 .debug_info
                                                 00010004
                                                           2**0
                  000002c8
                            00000000
                                      00000000
                  CONTENTS, READONLY, DEBUGGING
                                                000102cc
 4 .debug_abbrev 000001b6
                            00000000 00000000
                                                           2**0
                  CONTENTS, READONLY, DEBUGGING
  5 .debug_loc
                  0000009c
                                                00010482
                            00000000
                                      00000000
                  CONTENTS, READONLY, DEBUGGING
 6 .debug_aranges 00000040 00000000
                                       00000000
                                                  0001051e 2**0
                  CONTENTS, READONLY, DEBUGGING
 7 .debug_line
                                                 0001055e
                                                           2**0
                  00000102
                            00000000
                                      00000000
                  CONTENTS,
                            READONLY, DEBUGGING
 8 .debug_str
                  0000017b
                                                 00010660
                                                           2**0
                            00000000
                                      00000000
                  CONTENTS, READONLY, DEBUGGING
 9 .comment
                  00000011 00000000
                                                 000107db
                                                           2**0
                                      00000000
                  CONTENTS, READONLY
 10 .ARM.attributes 00000033
                                                             2**0
                              00000000
                                        00000000
                                                   000107ec
                  CONTENTS, READONLY
                                                00010820
 11 .debug_frame
                  00000078 00000000
                                      00000000
                  CONTENTS, READONLY, DEBUGGING
```

Symbols of learn-in-depth-cortex-m3.elf

```
$ arm-none-eabi-nm.exe learn_in_depth_cortex_m3.elf
20000004 B E bss
20000004 D E data
08000180 T _E_text
20000004 B _S_bss
20000000 D _S_data
20001004 B _stack_top
08000174 W Bus_Handler
08000174 T default handler
08000174 W H_Fault_handler
08000018 T main
08000174 W NMI_Handler
20000000 D R_ODR
080000c0 T Reset_Handler
08000174 W Usage_Fault_handler
08000000 T vectors
```