LAPORAN PRAKTIKUM
INSTALASI & KONFIGURASI FTP SERVER

OLEH:

AISA SILVANA S. NABABAN

43324011

D3 TEKNOLOGI KOMPUTER

INSTITUT TEKNOLOGI DEL

2026

INSTALASI & KONFIGURASI FTP SERVER DI UBUNTU SERVER

1. Install FTP Server menggunakan package VSFTPD (Very Secure FTP Daemon) dengan perintah

```
aisasilvana@aisasilvana:~$ sudo apt install vsftpd
Reading package lists... Done
Building dependency tree... Done
Reading state information... Done
The following NEW packages will be installed:
  vsftpd
0 upgraded, 1 newly installed, 0 to remove and 53 not upgraded.
Need to get 120 kB of archives.
After this operation, 312 kB of additional disk space will be used.
Get:1 http://id.archive.ubuntu.com/ubuntu noble-updates/main amd64 vsftpd amd64 3.0.5-0ubuntu3.
Fetched 120 kB in 2s (68,8 kB/s)
Prakonfigurasi paket ...
Selecting previously unselected package vsftpd.
(Sedang membaca basis data ...  127465 berkas atau direktori telah terpasang.)
Preparing to unpack .../vsftpd_3.0.5-0ubuntu3.1_amd64.deb ...
Unpacking vsftpd (3.0.5-0ubuntu3.1) ...
Sedang menata vsftpd (3.0.5-0ubuntu3.1) ...

Progress: [ 40%] [#########################################################.....................
```

2. Setelah instalasi selesai, cek status service FTP

```
aisasilvana@aisasilvana:~$ sudo systemctl start vsftpd
aisasilvana@aisasilvana:~$ sudo systemctl enable vsftpd
Synchronizing state of vsftpd.service with SysV service script with /usr/lib/systemd/systemd-sysv-install.
Executing: /usr/lib/systemd/systemd-sysv-install enable vsftpd
aisasilvana@aisasilvana:~$
```

```
aisasilvana@aisasilvana:~$ sudo systemctl status vsftpd
● vsftpd.service - vsftpd FTP server
     Loaded: loaded (/usr/lib/systemd/system/vsftpd.service; enabled; preset: enabled)
     Active: active (running) since Thu 2026-04-23 07:11:03 UTC; 4min 18s ago
   Main PID: 2878 (vsftpd)
      Tasks: 1 (limit: 4544)
     Memory: 720.0K (peak: 1.5M)
        CPU: 16ms
     CGroup: /system.slice/vsftpd.service
             └─2878 /usr/sbin/vsftpd /etc/vsftpd.conf

Apr 23 07:11:03 aisasilvana systemd[1]: Starting vsftpd.service - vsftpd FTP server...
Apr 23 07:11:03 aisasilvana systemd[1]: Started vsftpd.service - vsftpd FTP server.
aisasilvana@aisasilvana:~$
```

3. Edit File Konfigurasi FTP

```
  GNU nano 7.2                                                    /etc/vsftpd.conf *
# Example config file /etc/vsftpd.conf
#
# The default compiled in settings are fairly paranoid. This sample file
# loosens things up a bit, to make the ftp daemon more usable.
# Please see vsftpd.conf.5 for all compiled in defaults.
#
# READ THIS: This example file is NOT an exhaustive list of vsftpd options.
# Please read the vsftpd.conf.5 manual page to get a full idea of vsftpd's
# capabilities.
#
#
# Run standalone?  vsftpd can run either from an inetd or as a standalone
# daemon started from an initscript.
listen=NO
#
# This directive enables listening on IPv6 sockets. By default, listening
# on the IPv6 "any" address (::) will accept connections from both IPv6
# and IPv4 clients. It is not necessary to listen on *both* IPv4 and IPv6
# sockets. If you want that (perhaps because you want to listen on specific
# addresses) then you must run two copies of vsftpd with two configuration
# files.
listen_ipv6=YES
#
# Allow anonymous FTP? (Disabled by default).
anonymous_enable=NO
#
# Uncomment this to allow local users to log in.
local_enable=YES
#
# Uncomment this to enable any form of FTP write command.
write_enable=YES
#
# Default umask for local users is 077. You may wish to change this to 022,
# if your users expect that (022 is used by most other ftpd's)
local_umask=022
#
```

```
# Uncomment this to indicate that vsftpd use a utf8 filesystem.
#utf8_filesystem=YES
chroot_local_user=YES
pasv_enable=YES
pasv_min_port=10000
pasv_max_port=10100
```

4. Setelah selesai mengedit konfigurasi, restart layanan FTP Kemudian cek kembali statusnya

```
aisasilvana@aisasilvana:~$ sudo systemctl restart vsftpd
aisasilvana@aisasilvana:~$ sudo systemctl status vsftpd
● vsftpd.service - vsftpd FTP server
     Loaded: loaded (/usr/lib/systemd/system/vsftpd.service; enabled; preset: enabled)
     Active: active (running) since Thu 2026-04-23 07:24:34 UTC; 5s ago
    Process: 3142 ExecStartPre=/bin/mkdir -p /var/run/vsftpd/empty (code=exited, status=0/SUCC
   Main PID: 3145 (vsftpd)
      Tasks: 1 (limit: 4544)
     Memory: 712.0K (peak: 1.7M)
        CPU: 18ms
     CGroup: /system.slice/vsftpd.service
             └─3145 /usr/sbin/vsftpd /etc/vsftpd.conf

Apr 23 07:24:34 aisasilvana systemd[1]: Starting vsftpd.service - vsftpd FTP server...
Apr 23 07:24:34 aisasilvana systemd[1]: Started vsftpd.service - vsftpd FTP server.
aisasilvana@aisasilvana:~$
```

5. Buat user baru khusus untuk FTP

```
aisasilvana@aisasilvana:~$ sudo adduser ftpuser
info: Adding user `ftpuser' ...
info: Selecting UID/GID from range 1000 to 59999 ...
info: Adding new group `ftpuser' (1001) ...
info: Adding new user `ftpuser' (1001) with group `ftpuser (1001)' ...
info: Creating home directory `/home/ftpuser' ...
info: Copying files from `/etc/skel' ...
New password:
Retype new password:
passwd: password updated successfully
Changing the user information for ftpuser
Enter the new value, or press ENTER for the default
        Full Name []: ftpuser
        Room Number []:
        Work Phone []:
        Home Phone []:
        Other []:
Is the information correct? [Y/n] y
info: Adding new user `ftpuser' to supplemental / extra groups `users' ...
info: Adding user `ftpuser' to group `users' ...
aisasilvana@aisasilvana:~$ _
```

6. Setelah user ftpuser berhasil dibuat, langkah berikutnya adalah membuat folder khusus untuk proses upload file pada FTP Server

```
aisasilvana@aisasilvana:~$ sudo mkdir -p /home/ftpuser/ftp/upload
aisasilvana@aisasilvana:~$
```

7. Agar folder dapat digunakan dengan benar oleh FTP Server, atur permission folder utama

```
aisasilvana@aisasilvana:~$ sudo chown root:root /home/ftpuser/ftp
aisasilvana@aisasilvana:~$
```

8. Selanjutnya atur folder upload agar user dapat menulis file

```
aisasilvana@aisasilvana:~$ sudo chmod 755 /home/ftpuser/ftp
aisasilvana@aisasilvana:~$ _
```

```
aisasilvana@aisasilvana:~$ sudo chown ftpuser:ftpuser /home/ftpuser/ftp/upload
aisasilvana@aisasilvana:~$
```

9. Berikan izin akses yang sesuai

```
aisasilvana@aisasilvana:~$ sudo chown root:root /home/ftpuser
aisasilvana@aisasilvana:~$ sudo chmod 755 /home/ftpuser
aisasilvana@aisasilvana:~$ _
```

10. Agar FTP Server dapat diakses dari komputer client, port layanan FTP perlu dibuka pada firewall menggunakan iptables

```
aisasilvana@aisasilvana:~$ sudo iptables -A INPUT -p tcp --dport 21 -j ACCEPT
aisasilvana@aisasilvana:~$ sudo iptables -A INPUT -p tcp --dport 10000:10100 -j ACCEPT
aisasilvana@aisasilvana:~$ sudo netfilter-persistent save
```

11. Setelah FTP Server selesai dikonfigurasi dan port FTP sudah dibuka, langkah berikutnya adalah melakukan pengujian koneksi dari komputer client.

```
aisasilvana@aisasilvana-VMware-Virtual-Platform:~$ ftp 192.168.100.1
Connected to 192.168.100.1.
220 (vsFTPd 3.0.5)
Name (192.168.100.1:aisasilvana): ftpuser
331 Please specify the password.
Password:
230 Login successful.
Remote system type is UNIX.
Using binary mode to transfer files.
ftp> bye
221 Goodbye.
aisasilvana@aisasilvana-VMware-Virtual-Platform:~$
```