CSE 1320 - Intermediate Programming

Data Types & Number Systems

Alex Dillhoff

University of Texas at Arlington

Numbers in Memory

Data is represented in memory dependent on the **type**. The **type** also determines how much memory they require.

There are several types in C:

- Scalar
- · Aggregate
- Functions
- Union
- Struct
- Void

Memory and C Programs

When a program is executed, two broad categories of data are placed in memory:

- 1. Object code The instructions which are executed.
- 2. Variables The individual data that are processed.

Representing Numbers

The lowest unit of memory is represented as a **bit**, which can either be 1 or 0.

The next largest unit of measurement for information is a **byte**, which consists of 8 bits.

Representing Numbers

Another unit of measurement for data is a **word**, which has a size dependent on a specific architecture.

Commonly, a **word** is designed to optimize at the hardware level. The size is usually chosen such that an entire instruction can be transferred in a single operation.

Sometimes the size represents the largest possible address size.

Representing Numbers

Any number can be conveniently represented as a combination of the multiples of each of the powers of the base.

Examples in base 10

•
$$212 = 2 * 10^2 + 1 * 10^1 + 2 * 10^0$$

•
$$1650 = 1 * 10^3 + 6 * 10^2 + 5 * 10^1 + 0 * 10^0$$

•
$$6 = 6 * 10^{0}$$

•
$$21 = 2 * 10^1 + 1 * 10^0$$

6

Representing Binary

Binary numbers can either be 0 or 1 for each power. They can be represented similarly to the approach taken in the previous slide.

Examples in base 2

- $2 = 1 * 2^1 + 0 * 2^0$
- $32 = 1 * 2^5 + 0 * 2^4 + 0 * 2^3 + 0 * 2^2 + 0 * 2^1 + 0 * 2^0$
- $\cdot 10 = 1 * 2^3 + 0 * 2^2 + 1 * 2^1 + 0 * 2^0$
- $5 = 1 * 2^2 + 0 * 2^1 + 1 * 2^0$

Converting from decimal to binary

Base Notation

When representing numbers from multiple systems, it is convenient to show the base of each number using a subscript.

- $\cdot 127_{10} = 1111111_2$
- $5_{10} = 101_2$
- $\cdot 256_{10} = 100000000_2$
- $3_{10} = 11_2$

Representing Hexadecimal

Hexadecimal numbers have digits that can be 0 - F, reflecting a base of 16.

The counting sequence of hexadecimal is 0-9 then A-F.

Examples in base 16

- $F = 15 * 16^0$
- $80 = 8 * 16^1 + 0 * 16^0$
- $FF = 15 * 16^1 + 15 * 16^0$
- A0E = $10 * 16^2 + 0 * 16^1 + 14 * 16^0$

Converting from decimal to hexadecimal

$$128_{10} = ?_{16}$$

Conversion: Divide by the base you are converting to. The remainder fills up the right-most digit.

$$\frac{128}{16} = 8$$
 remainder 0

Converting from decimal to hexadecimal

$$128_{10} = ?_{16}$$

Conversion: Divide by the base you are converting to. The remainder fills up the right-most digit.

$$\frac{128}{16} = 8 \text{ remainder } 0$$

Take the remaining value, 8, and divide again, placing the remainder in the next position.

$$\frac{8}{16} = 0$$
 remainder 8

Result: $128_{10} = 80_{16}$

Converting from decimal to hexadecimal

$$312_{10} = ?_{16}$$

$$\frac{312}{16}$$
 = 19 remainder 8

Intermediate Result: 8₁₆

$$\frac{19}{16} = 1$$
 remainder 3

Intermediate Result: 38₁₆

$$\frac{1}{16} = 0$$
 remainder 1

Final Result: 138₁₆

Scalar Types in C

- · C supports character, integer, and scalar types.
- Each type has a minimum size.
- Character and integer types can either be signed or unsigned.

Scalar Types in C

Integer types can represent a range of numbers dependent on their size.

For example, an integer type with a size in m bits can represent a range of $[-2^{m-1}-1,2^{m-1}-1]$ for **signed** types and $[0,2^m-1]$ for **unsigned** types.

Scalar Types in C

 $\verb|https://en.wikipedia.org/wiki/C_data_types|\\$

Signed versus Unsigned Types

An **int** is a **signed** type, meaning it can represent both positive and negative numbers.

The minimum bit size of an **int** is 16 bits.

Signed Types

The left-most bit in a signed type is called the sign bit.

A 1 signifies a negative value, and a 0 is a positive value.

Examples

- $0111_2 = 7_{10}$
- $1111_2 = -7_{10}$

Example: rollover.c

Example: sizeof.c

Type Conversions

There are two approaches to converting a value from one type to another:

- 1. Automatic Type Conversion
- 2. Forced Type Conversion

Automatic Type Conversion

- · Every expression has an associated type.
- Expressions resulting from logical or relational operators have type int.
- All values of char or short are promoted to int before processing.

Dominating Types

Automatic conversions involving mixed types acted upon by a binary operation generally follow the following prioritization:

- 1. long double
- 2. double
- 3. float
- 4. unsigned long
- 5. **long**
- 6. unsigned
- 7. **int**

Automatic Type Conversions

Further reading: Chapter 3.10

Example: auto_convert.c

Forced Type Conversions

Individual expressions and values can be cast to a different type using the following syntax:

Syntax

```
(type) var;
```

Example

```
float a = 3.1;
printf("a as an int is %d\n", (int) a);
```