

CONSOLE VIA IP CONFIGURED ON THE ROUTER INTERFACE - OUTPUT:

labs.surennetwork.com/legacy/topology

Paused

Notifications

ROUTER

```
ROUTER>en
ROUTER#sh ip int bri
Interface                IP-Address      OK? Method Status      Protocol
Ethernet0/0              unassigned      YES manual  up          up
Ethernet0/1              unassigned      YES TFTP    down        down
Ethernet0/2              unassigned      YES TFTP    down        down
Ethernet0/3              unassigned      YES TFTP    down        down
ROUTER#conf t
Enter configuration commands, one per line. End with CNTL/Z.
ROUTER(config)#
ROUTER(config)#int eth 0/0
ROUTER(config-if)#ip add 50.0.0.1 255.0.0.0
ROUTER(config-if)#exit
ROUTER(config)#exit
ROUTER#
*Aug 17 09:44:29.155: %SYS-5-CONFIG_I: Configured from console by console
ROUTER#
ROUTER#sh ip int bri
Interface                IP-Address      OK? Method Status      Protocol
Ethernet0/0              50.0.0.1        YES manual  up          up
Ethernet0/1              unassigned      YES TFTP    down        down
Ethernet0/2              unassigned      YES TFTP    down        down
Ethernet0/3              unassigned      YES TFTP    down        down
ROUTER#
```

Router Configuration

Physical

01 : 00 : 00 START

37°C Partly sunny

Search

15:15 17-08-2026

UEM & PREVILAGE AUTHENTICATION CREATETION OUT PUT:-

The screenshot displays a network simulation environment. A terminal window titled "ROUTER" is open, showing the following text:

```
Press RETURN to get started.  
  
User Access Verification  
Username: admin  
Password:  
ROUTER>enable  
Password:  
ROUTER#
```

The terminal window is overlaid on a larger window that shows a partial logo "SN".

At the bottom of the screen is a Windows taskbar. On the left, it shows the weather: 37°C, Partly sunny. In the center is a search bar labeled "Search". On the right, there is a "Router Configuration" button, a "Physical" button, a volume slider, a timer set to "01 : 00 : 00", and a "START" button. The system clock in the bottom right corner shows "15:37" and "17-08-2026".

IP CONFIGURED AT PC AND NETWORK REACHABILITY CHECK OUTPUT:-

The screenshot displays a network simulation environment. On the left, a terminal window titled 'ROUTER' shows the following output:

```
Press RETURN to get started.

User Access Verification

Username: admin
Password:
ROUTER>en
Password:
ROUTER#ping 50.0.0.10
Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 50.0.0.10, timeout is 2 seconds:
!!!!
Success rate is 100 percent (5/5), round-trip min/avg/max = 1/1/2 ms
ROUTER#
```

On the right, a 'QEMU (Win)' window shows a Windows desktop. An 'Administrator: Command Prompt' window is open, displaying the following output:

```
Tunnel adapter {42A1F8B7-30A8-4EF7-81AF-C694F5F3D81B}:
Media State . . . . . : Media disconnected
Connection-specific DNS Suffix . :
Tunnel adapter 6T04 Adapter:
Connection-specific DNS Suffix . :
IPv6 Address . . . . . : 2002:3200:a::3200:a
Default Gateway . . . . . :
C:\Users\User>ping 50.0.0.1

Pinging 50.0.0.1 with 32 bytes of data:
Reply from 50.0.0.1: bytes=32 time=2ms TTL=255
Reply from 50.0.0.1: bytes=32 time=1ms TTL=255
Reply from 50.0.0.1: bytes=32 time<1ms TTL=255
Reply from 50.0.0.1: bytes=32 time=1ms TTL=255

Ping statistics for 50.0.0.1:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 0ms, Maximum = 2ms, Average = 1ms
C:\Users\User>
```

At the bottom of the interface, there is a 'Router Configuration' tab and a 'Physical' tab. The 'Physical' tab shows a timeline with a 'START' button and a duration of '01 : 00 : 00'. The system tray at the bottom indicates a temperature of 37°C, 'Partly sunny' weather, and the date '17-08-2026' at '15:54'.

TELNET ENABLED & AUTHENTICATION CREATED AND LOGIN THE ROUTER VIA TELNET OUTPUT:-

The screenshot displays a virtual network lab environment. At the top, a browser window shows the URL `labs.surrennetwork.com/legacy/topology`. The main workspace features a grid background with a large window titled "QEMU (Win)" representing a virtual machine. Inside this window is a Windows desktop with a blue background and icons for "Computer" and "Kiwi Syslog Server Co...". Overlaid on the desktop is a PuTTY terminal window titled "50.0.0.1 - PuTTY". The terminal displays the following text:

```
User Access Verification
Password:
ROUTER>en
ROUTER>enable
Password:
ROUTER#
```

Below the QEMU window, a taskbar shows various application icons and the system clock at 10:56 AM. At the bottom of the interface, there is a "Router Configuration" button on the left, a "Physical" button with a search icon and a slider in the center, and a timer showing "01 : 00 : 00" with a "START" button on the right. The bottom-most bar includes a weather widget showing "37°C Partly sunny", a search bar, and a row of application icons.