### **Download TWS**

- 1. Go to: <a href="https://www.interactivebrokers.com/en/index.php?f=16040">https://www.interactivebrokers.com/en/index.php?f=16040</a>
- 2. Scroll down and select "Download for Other Operating Systems"
- 3. Download Windows 32-bit
- 4. Next, go to <a href="http://interactivebrokers.github.io/">http://interactivebrokers.github.io/</a>
- 5. Select "I Agree"
- 6. Choose "IB API Stable for Windows" and download

### **Configure TWS**

- 1. Launch TWS and sign in
- 2. Navigate to File -> Global Configuration -> API -> Settings
- 3. Ensure the following are all checked:
  - Enable ActiveX and Socket Clients
  - Enable DDE Clients
  - Download open orders on connection
- 4. Socket Port should be set to: 7497
- 5. Master API client ID should be set to: 0
- 6. "Allow connections from localhost only" should be checked
- 7. TWS is now configured

## **Download AutoBroker**

- 1. <a href="https://fusautobrokers.slack.com/messages/CJQS5BTBK/">https://fusautobrokers.slack.com/messages/CJQS5BTBK/</a>
- 2. Download AutoBroker.zip
- 3. Open downloaded .zip file
- 4. Move AutoBroker folder to Desktop

# **Configure AutoBroker**

- Navigate to Desktop and open AutoBroker folder
- 2. Right click Run AutoBroker and click edit. If prompted, edit with notepad
- On line 3, replace \*your filepath to AutoBroker;example:Users\yourUser\Desktop\AutoBroker\* with your specific filepath and save and exit
- 4. Now, right click Run TWS and select edit

- 5. On line 4, input your username and password. Example: username:admin password:admin . Save and exit
- 6. Now, right click settings and select edit
- 7. In this file, you can edit your Portfolio size, Rounding quantities, Primary Order types, Auxiliary Order types, Order Durations, and Order Time Parameters. Save and exit
- 8. Finally, access the tickers Excel file. This is where you can input new tickers or remove tickers for analysis. There is no limitation to ticker quantity. Save when finished

## **Run AutoBroker Manually**

- 1. To run AutoBroker, navigate to Desktop-> AutoBroker -> Settings
- 2. Run Run TWS first and allow it to open fully
- 3. Next, run Run AutoBroker

## **Run AutoBroker Automatically**

- 1. From the Start Menu, search for Task Scheduler and launch
- 2. On the right-hand side, select Create a Basic Task
- 3. Name your task Run TWS and add a description if desired
- 4. Next, select how frequently you would like this program to run
  - a. Then, specify exact time parameters such as time and day(s) of the week
- 5. Next, select start a program
  - a. Select Browse and navigate to Desktop->AutoBroker->Settings->Run TWS
- 6. Select Next and Finished
- 7. Repeat steps 1-6 for Run AutoBroker
  - a. NOTE: It is advised to schedule Run AutoBroker at least 5 minutes **AFTER** Run TWS to give TWS enough time to load

## **Important Notes**

When running AutoBroker for the first time, follow the steps under <u>Run</u>
<u>AutoBroker Manually</u>. This will allow <u>AutoBroker</u> to acclimate to your
computer and give you time to allow permissions should your firewall
prompt you.

- If you have Two-Factor Authentication on, AutoBroker will not be able to sign you in. This means AutoBroker will not be completely autonomous. If you wish to have complete automation, disable Two-Factor Authentication.
  Warning: Disabling Two-Factor Authentication removes a layer of account security. If you do not wish to remove Two-Factor Authentication, please follow the steps under Run AutoBroker Manually.
- Do not have any trades currently active/pending while starting AutoBroker. This will disrupt the algorithms generating the target portfolio and could also interrupt the pending orders.