

```
HO-EDGE#
HO-EDGE#
HO-EDGE#
HO-EDGE#int e0/0
^
% Invalid input detected at '^' marker.

HO-EDGE#conf t
Enter configuration commands, one per line. End with CNTL/Z.
HO-EDGE(config)#int e0/0
HO-EDGE(config-if)#ip add 10.0.0.1 255.0.0.0
HO-EDGE(config-if)#no sh
HO-EDGE(config-if)#int e0/1
HO-EDGE(config-if)#ip add 20.0.0.1 255.0.0.0
HO-EDGE(config-if)#no sh
HO-EDGE(config-if)#exit
HO-EDGE(config)#ip dhcp pool Win
HO-EDGE(dhcp-config)#network 10.0.0.0
HO-EDGE(dhcp-config)#default-router 10.0.0.1
HO-EDGE(dhcp-config)#dns-server 8.8.8.8
HO-EDGE(dhcp-config)#exit
HO-EDGE(config)#
*Aug  5 17:22:58.500: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped (Config Wizard)
HO-EDGE(config)#access-list 10 permit 10.0.0.0 0.255.255.255
HO-EDGE(config)#int e0/0
HO-EDGE(config-if)#ip nat inside
HO-EDGE(config-if)#ex
*Aug  5 17:25:22.220: %LINEPROTO-5-UPDOWN: Line protocol on Interface NVI0, changed state to up
HO-EDGE(config-if)#int e0/1
HO-EDGE(config-if)#ip nat outside
HO-EDGE(config-if)#exit
HO-EDGE(config)#ip nat inside source list 10 int e0/1 overload
```



Search




ENG
IN




11:01 PM
8/5/2026

```
HO-EDGE#
HO-EDGE#
HO-EDGE#
HO-EDGE#int e0/0
^
% Invalid input detected at '^' marker.

HO-EDGE#conf t
Enter configuration commands, one per line. End with CNTL/Z.
HO-EDGE(config)#int e0/0
HO-EDGE(config-if)#ip add 10.0.0.1 255.0.0.0
HO-EDGE(config-if)#no sh
HO-EDGE(config-if)#int e0/1
HO-EDGE(config-if)#ip add 20.0.0.1 255.0.0.0
HO-EDGE(config-if)#no sh
HO-EDGE(config-if)#exit
HO-EDGE(config)#ip dhcp pool Win
HO-EDGE(dhcp-config)#network 10.0.0.0
HO-EDGE(dhcp-config)#default-router 10.0.0.1
HO-EDGE(dhcp-config)#dns-server 8.8.8.8
HO-EDGE(dhcp-config)#exit
HO-EDGE(config)#
*Aug  5 17:22:58.500: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped (Config Wizard)
HO-EDGE(config)#access-list 10 permit 10.0.0.0 0.255.255.255
HO-EDGE(config)#int e0/0
HO-EDGE(config-if)#ip nat inside
HO-EDGE(config-if)#ex
*Aug  5 17:25:22.220: %LINEPROTO-5-UPDOWN: Line protocol on Interface NV10, changed state to up
HO-EDGE(config-if)#int e0/1
HO-EDGE(config-if)#ip nat outside
HO-EDGE(config-if)#exit
HO-EDGE(config)#ip nat inside source list 10 int e0/1 overload
HO-EDGE(config)#
HO-EDGE#
```





```
DC-EDGE
DC-EDGE#
DC-EDGE#sh ip nat ?
nvi          NVI information
redundancy   NAT HA redundancy
statistics    Translation statistics
translations  Translation entries

DC-EDGE#sh ip nat tra
DC-EDGE#sh ip nat translations
Pro Inside global      Inside local      Outside local      Outside global
--- 30.0.0.10          192.168.1.10      ---              ---
--- 30.0.0.20          192.168.1.20      ---              ---
DC-EDGE#sh ip int brief
Interface          IP-Address      OK? Method Status      Prot
---
Gig0/1              192.168.1.1     YES manual up          up
Ethernet0/0         192.168.1.1     YES manual up          up
Ethernet0/1         30.0.0.2        YES manual up          up
Ethernet0/2         unassigned      YES TFTP  down        down
Ethernet0/3         unassigned      YES TFTP  down        down
NVI0                192.168.1.1     YES unset up          up

DC-EDGE#sh ip route
Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2
       i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2
       ia - IS-IS inter area, * - candidate default, U - per-user static route
       o - ODR, P - periodic downloaded static route, H - NHRP, l - LISP
       a - application route
       + - replicated route, % - next hop override, p - overrides from PfR

Gateway of last resort is 30.0.0.1 to network 0.0.0.0

S*    0.0.0.0/0 [1/0] via 30.0.0.1
C     30.0.0.0/8 is variably subnetted, 4 subnets, 2 masks
L     30.0.0.0/8 is directly connected, Ethernet0/1
L     30.0.0.2/32 is directly connected, Ethernet0/1
L     30.0.0.10/32 is directly connected, Ethernet0/1
L     30.0.0.20/32 is directly connected, Ethernet0/1
C     192.168.1.0/24 is variably subnetted, 2 subnets, 2 masks
L     192.168.1.0/24 is directly connected, Ethernet0/0
L     192.168.1.1/32 is directly connected, Ethernet0/0
DC-EDGE#
```



VPC1



ailed

Bad command: "pipe2 failed". Use ? for help.

VPC1>

VPC1> sh ip

NAME : VPC1[1]
IP/MASK : 192.168.1.10/24
GATEWAY : 192.168.1.1
DNS :
MAC : 00:50:79:66:68:e2
LPORT : 20000
RHOST:PORT : 127.0.0.1:30000
MTU : 1500

VPC1> █

VPC2

Bad command: "pipe2 failed". Use ? for help.

VPC2>

VPC2>

VPC2> sh ip

NAME : VPC2[1]
IP/MASK : 192.168.1.20/24
GATEWAY : 192.168.1.1
DNS :
MAC : 00:50:79:66:68:e3
LPORT : 20000
RHOST:PORT : 127.0.0.1:30000
MTU : 1500

VPC2> █

